

Abstract

This is the MySQL Security Guide extract from the MySQL 5.6 Reference Manual.

For legal information, see the Legal Notices.

For help with using MySQL, please visit either the MySQL Forums or MySQL Mailing Lists, where you can discuss your issues with other MySQL users.

For additional documentation on MySQL products, including translations of the documentation into other languages, and downloadable versions in variety of formats, including HTML and PDF formats, see the MySQL Documentation Library.

Licensing information—MySQL 5.6. This product may include third-party software, used under license. If you are using a *Commercial* release of MySQL 5.6, see this document for licensing information, including licensing information relating to third-party software that may be included in this Commercial release. If you are using a *Community* release of MySQL 5.6, see this document for licensing information, including licensing information relating to third-party software that may be included in this Community release.

Licensing information—MySQL Cluster. This product may include third-party software, used under license. If you are using a *Commercial* release of MySQL Cluster NDB 7.3 or NDB 7.4, see this document for licensing information, including licensing information relating to third-party software that may be included in this Commercial release. If you are using a *Community* release of MySQL Cluster NDB 7.3 or NDB 7.4, see this document for licensing information, including licensing information relating to third-party software that may be included in this Community release.

Document generated on: 2016-06-03 (revision: 47903)

Table of Contents

Preface and Legal Notices	۰۰۰۰ ۱
1 Security	1
2 General Security Issues	3
2.1 Security Guidelines	
2.2 Keeping Passwords Secure	
2.2.1 End-User Guidelines for Password Security	
2.2.2 Administrator Guidelines for Password Security	
2.2.3 Passwords and Logging	
2.2.4 Password Hashing in MySQL	
2.2.5 Implications of Password Hashing Changes in MySQL 4.1 for Application Programs	
2.2.3 Implications of Password Hashing Changes in MySQL 4.1 for Application Programs	
2.4 Security-Related mysqld Options and Variables	
2.5 How to Run MySQL as a Normal User	
2.6 Security Issues with LOAD DATA LOCAL	
2.7 Client Programming Security Guidelines	
3 Postinstallation Setup and Testing	
3.1 Initializing the Data Directory	
3.1.1 Problems Running mysql_install_db	
3.2 Starting the Server	. 23
3.2.1 Troubleshooting Problems Starting the MySQL Server	
3.3 Testing the Server	
3.4 Securing the Initial MySQL Accounts	
3.5 Starting and Stopping MySQL Automatically	
4 The MySQL Access Privilege System	
4.1 Privileges Provided by MySQL	36
4.2 Grant Tables	40
4.3 Specifying Account Names	. 46
4.4 Access Control, Stage 1: Connection Verification	48
4.5 Access Control, Stage 2: Request Verification	
4.6 When Privilege Changes Take Effect	
4.7 Troubleshooting Problems Connecting to MySQL	
5 MySQL User Account Management	
5.1 User Names and Passwords	
5.2 Adding User Accounts	
5.3 Removing User Accounts	
5.4 Setting Account Resource Limits	
5.5 Assigning Account Passwords	
5.6 Password Expiration and Sandbox Mode	
·	
5.7 Pluggable Authentication	
5.8 Proxy Users	
5.9 Using Secure Connections	
5.9.1 OpenSSL Versus yaSSL	
5.9.2 Building MySQL with Support for Secure Connections	
5.9.3 Secure Connection Protocols and Ciphers	
5.9.4 Configuring MySQL to Use Secure Connections	
5.9.5 Command Options for Secure Connections	
5.10 Creating SSL and RSA Certificates and Keys	
5.10.1 Creating SSL Certificates and Keys Using openssl	
5.10.2 Creating RSA Keys Using openssl	
5.11 Connecting to MySQL Remotely from Windows with SSH	92
5.12 SQL-Based MySQL Account Activity Auditing	93

Security in MySQL

6 Security Plugins	95
6.1 Authentication Plugins	. 96
6.1.1 The Native Authentication Plugin	. 96
6.1.2 The Old Native Authentication Plugin	. 96
6.1.3 Migrating Away from Pre-4.1 Password Hashing and the mysql_old_password Plugin	
6.1.4 The SHA-256 Authentication Plugin	
6.1.5 The PAM Authentication Plugin	104
6.1.6 The Windows Native Authentication Plugin	112
6.1.7 The Cleartext Client-Side Authentication Plugin	117
6.1.8 The Socket Peer-Credential Authentication Plugin	118
6.1.9 The Test Authentication Plugin	118
6.2 The Password Validation Plugin	119
6.2.1 Password Validation Plugin Installation	120
6.2.2 Password Validation Plugin Options and Variables	120
6.3 MySQL Enterprise Audit	125
6.3.1 Installing MySQL Enterprise Audit	
6.3.2 MySQL Enterprise Audit Security Considerations	128
6.3.3 The Audit Log File	128
6.3.4 Audit Log Logging Control	138
6.3.5 Audit Log Filtering	140
6.3.6 Audit Log Reference	142
6.3.7 Audit Log Restrictions	151
6.4 MySQL Enterprise Firewall	151
6.4.1 MySQL Enterprise Firewall Components	152
6.4.2 Installing or Uninstalling MySQL Enterprise Firewall	152
6.4.3 Using MySQL Enterprise Firewall	
6.4.4 MySQL Enterprise Firewall Reference	159
A MySQL 5.6 FAQ: Security	165

Preface and Legal Notices

This is the MySQL Security Guide extract from the MySQL 5.6 Reference Manual.

Legal Notices

Copyright © 1997, 2016, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at

http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit

http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info or visit http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs if you are hearing impaired.

This documentation is NOT distributed under a GPL license. Use of this documentation is subject to the following terms:

You may create a printed copy of this documentation solely for your own personal use. Conversion to other formats is allowed as long as the actual content is not altered or edited in any way. You shall not publish or distribute this documentation in any form or on any media, except if you distribute the documentation in a manner similar to how Oracle disseminates it (that is, electronically for download on a Web site with the software) or on a CD-ROM or similar medium, provided however that the documentation is disseminated together with the software on the same medium. Any other use, such as any dissemination of printed copies or use of this documentation, in whole or in part, in another publication, requires the prior written consent from an authorized representative of Oracle. Oracle and/or its affiliates reserve any and all rights to this documentation not expressly granted above.

Chapter 1 Security

When thinking about security within a MySQL installation, you should consider a wide range of possible topics and how they affect the security of your MySQL server and related applications:

- General factors that affect security. These include choosing good passwords, not granting unnecessary
 privileges to users, ensuring application security by preventing SQL injections and data corruption, and
 others. See Chapter 2, General Security Issues.
- Security of the installation itself. The data files, log files, and the all the application files of your installation should be protected to ensure that they are not readable or writable by unauthorized parties. For more information, see Chapter 3, *Postinstallation Setup and Testing*.
- Access control and security within the database system itself, including the users and databases
 granted with access to the databases, views and stored programs in use within the database. For more
 information, see Chapter 4, The MySQL Access Privilege System, and Chapter 5, MySQL User Account
 Management.
- The features offered by security-related plugins. See Chapter 6, Security Plugins.
- Network security of MySQL and your system. The security is related to the grants for individual users, but you may also wish to restrict MySQL so that it is available only locally on the MySQL server host, or to a limited set of other hosts.
- Ensure that you have adequate and appropriate backups of your database files, configuration and log
 files. Also be sure that you have a recovery solution in place and test that you are able to successfully
 recover the information from your backups. See Backup and Recovery.

	2	

Chapter 2 General Security Issues

Table of Contents

Security Guidelines	3
Reeping Passwords Secure	5
2.2.1 End-User Guidelines for Password Security	5
2.2.2 Administrator Guidelines for Password Security	6
2.2.3 Passwords and Logging	6
2.2.4 Password Hashing in MySQL	7
2.2.5 Implications of Password Hashing Changes in MySQL 4.1 for Application Programs	13
B Making MySQL Secure Against Attackers	13
Security-Related mysqld Options and Variables	15
How to Run MySQL as a Normal User	16
Security Issues with LOAD DATA LOCAL	16
Client Programming Security Guidelines	17

This section describes general security issues to be aware of and what you can do to make your MySQL installation more secure against attack or misuse. For information specifically about the access control system that MySQL uses for setting up user accounts and checking database access, see Chapter 3, Postinstallation Setup and Testing.

For answers to some questions that are often asked about MySQL Server security issues, see Appendix A, MySQL 5.6 FAQ: Security.

2.1 Security Guidelines

Anyone using MySQL on a computer connected to the Internet should read this section to avoid the most common security mistakes.

In discussing security, it is necessary to consider fully protecting the entire server host (not just the MySQL server) against all types of applicable attacks: eavesdropping, altering, playback, and denial of service. We do not cover all aspects of availability and fault tolerance here.

MySQL uses security based on Access Control Lists (ACLs) for all connections, queries, and other operations that users can attempt to perform. There is also support for SSL-encrypted connections between MySQL clients and servers. Many of the concepts discussed here are not specific to MySQL at all; the same general ideas apply to almost all applications.

When running MySQL, follow these guidelines:

- Do not ever give anyone (except MySQL root accounts) access to the user table in the mysql database! This is critical.
- Learn how the MySQL access privilege system works (see Chapter 4, The MySQL Access Privilege System). Use the GRANT and REVOKE statements to control access to MySQL. Do not grant more privileges than necessary. Never grant privileges to all hosts.

Checklist:

• Try mysql -u root. If you are able to connect successfully to the server without being asked for a password, anyone can connect to your MySQL server as the MySQL root user with full privileges! Review the MySQL installation instructions, paying particular attention to the information about setting a root password. See Section 3.4, "Securing the Initial MySQL Accounts".

- Use the SHOW GRANTS statement to check which accounts have access to what. Then use the REVOKE statement to remove those privileges that are not necessary.
- Do not store cleartext passwords in your database. If your computer becomes compromised, the intruder
 can take the full list of passwords and use them. Instead, use SHA2(), SHA1(), MD5(), or some other
 one-way hashing function and store the hash value.

To prevent password recovery using rainbow tables, do not use these functions on a plain password; instead, choose some string to be used as a salt, and use hash(hash(password)+salt) values.

- Do not choose passwords from dictionaries. Special programs exist to break passwords. Even passwords like "xfish98" are very bad. Much better is "duag98" which contains the same word "fish" but typed one key to the left on a standard QWERTY keyboard. Another method is to use a password that is taken from the first characters of each word in a sentence (for example, "Four score and seven years ago" results in a password of "Fsasya"). The password is easy to remember and type, but difficult to guess for someone who does not know the sentence. In this case, you can additionally substitute digits for the number words to obtain the phrase "4 score and 7 years ago", yielding the password "4sa7ya" which is even more difficult to guess.
- Invest in a firewall. This protects you from at least 50% of all types of exploits in any software. Put MySQL behind the firewall or in a demilitarized zone (DMZ).

Checklist:

Try to scan your ports from the Internet using a tool such as nmap. MySQL uses port 3306 by default.
 This port should not be accessible from untrusted hosts. As a simple way to check whether your MySQL port is open, try the following command from some remote machine, where server_host is the host name or IP address of the host on which your MySQL server runs:

```
shell> telnet server_host 3306
```

If telnet hangs or the connection is refused, the port is blocked, which is how you want it to be. If you get a connection and some garbage characters, the port is open, and should be closed on your firewall or router, unless you really have a good reason to keep it open.

- Applications that access MySQL should not trust any data entered by users, and should be written using proper defensive programming techniques. See Section 2.7, "Client Programming Security Guidelines".
- Do not transmit plain (unencrypted) data over the Internet. This information is accessible to everyone
 who has the time and ability to intercept it and use it for their own purposes. Instead, use an encrypted
 protocol such as SSL or SSH. MySQL supports internal SSL connections. Another technique is to use
 SSH port-forwarding to create an encrypted (and compressed) tunnel for the communication.
- Learn to use the tcpdump and strings utilities. In most cases, you can check whether MySQL data streams are unencrypted by issuing a command like the following:

```
shell> tcpdump -l -i eth0 -w - src or dst port 3306 | strings
```

This works under Linux and should work with small modifications under other systems.

Warning

If you do not see cleartext data, this does not always mean that the information actually is encrypted. If you need high security, consult with a security expert.

2.2 Keeping Passwords Secure

Passwords occur in several contexts within MySQL. The following sections provide guidelines that enable end users and administrators to keep these passwords secure and avoid exposing them. There is also a discussion of how MySQL uses password hashing internally and of a plugin that you can use to enforce stricter passwords.

2.2.1 End-User Guidelines for Password Security

MySQL users should use the following guidelines to keep passwords secure.

When you run a client program to connect to the MySQL server, it is inadvisable to specify your password in a way that exposes it to discovery by other users. The methods you can use to specify your password when you run client programs are listed here, along with an assessment of the risks of each method. In short, the safest methods are to have the client program prompt for the password or to specify the password in a properly protected option file.

- Use the mysql_config_editor utility, which enables you to store authentication credentials in an encrypted login path file named .mylogin.cnf. The file can be read later by MySQL client programs to obtain authentication credentials for connecting to MySQL Server. See mysql_config_editor MySQL Configuration Utility.
- Use a -pyour_pass or --password=your_pass option on the command line. For example:

```
shell> mysql -u francis -pfrank db_name
```

This is convenient *but insecure*. On some systems, your password becomes visible to system status programs such as ps that may be invoked by other users to display command lines. MySQL clients typically overwrite the command-line password argument with zeros during their initialization sequence. However, there is still a brief interval during which the value is visible. Also, on some systems this overwriting strategy is ineffective and the password remains visible to ps. (SystemV Unix systems and perhaps others are subject to this problem.)

If your operating environment is set up to display your current command in the title bar of your terminal window, the password remains visible as long as the command is running, even if the command has scrolled out of view in the window content area.

• Use the -p or --password option on the command line with no password value specified. In this case, the client program solicits the password interactively:

```
shell> mysql -u francis -p db_name
Enter password: *******
```

The "*" characters indicate where you enter your password. The password is not displayed as you enter it.

It is more secure to enter your password this way than to specify it on the command line because it is not visible to other users. However, this method of entering a password is suitable only for programs that you run interactively. If you want to invoke a client from a script that runs noninteractively, there is no opportunity to enter the password from the keyboard. On some systems, you may even find that the first line of your script is read and interpreted (incorrectly) as your password.

• Store your password in an option file. For example, on Unix, you can list your password in the [client] section of the .my.cnf file in your home directory:

```
[client]
password=your_pass
```

To keep the password safe, the file should not be accessible to anyone but yourself. To ensure this, set the file access mode to 400 or 600. For example:

```
shell> chmod 600 .my.cnf
```

To name from the command line a specific option file containing the password, use the --defaults-file=file_name option, where file_name is the full path name to the file. For example:

```
shell> mysql --defaults-file=/home/francis/mysql-opts
```

Using Option Files, discusses option files in more detail.

• Store your password in the MYSQL_PWD environment variable. See Environment Variables.

This method of specifying your MySQL password must be considered *extremely insecure* and should not be used. Some versions of ps include an option to display the environment of running processes. On some systems, if you set $\texttt{MYSQL_PWD}$, your password is exposed to any other user who runs ps. Even on systems without such a version of ps, it is unwise to assume that there are no other methods by which users can examine process environments.

On Unix, the mysql client writes a record of executed statements to a history file (see mysql Logging). By default, this file is named .mysql_history and is created in your home directory. Passwords can be written as plain text in SQL statements such as CREATE USER, GRANT, and SET PASSWORD, so if you use these statements, they are logged in the history file. To keep this file safe, use a restrictive access mode, the same way as described earlier for the .my.cnf file.

If your command interpreter is configured to maintain a history, any file in which the commands are saved will contain MySQL passwords entered on the command line. For example, bash uses ~/.bash_history. Any such file should have a restrictive access mode.

2.2.2 Administrator Guidelines for Password Security

Database administrators should use the following guidelines to keep passwords secure.

MySQL stores passwords for user accounts in the <code>mysql.user</code> table. Access to this table should never be granted to any nonadministrative accounts.

Account passwords can be expired so that users must reset them. See Section 5.6, "Password Expiration and Sandbox Mode".

The validate_password plugin can be used to enforce a policy on acceptable password. See Section 6.2, "The Password Validation Plugin".

A user who has access to modify the plugin directory (the value of the plugin_dir system variable) or the my.cnf file that specifies the location of the plugin directory can replace plugins and modify the capabilities provided by plugins, including authentication plugins.

Files such as log files to which passwords might be written should be protected. See Section 2.2.3, "Passwords and Logging".

2.2.3 Passwords and Logging

Passwords can be written as plain text in SQL statements such as CREATE USER, GRANT, SET PASSWORD, and statements that invoke the PASSWORD() function. If such statements are logged by the MySQL server as written, passwords in them become visible to anyone with access to the logs.

Beginning with MySQL 5.6.3, statement logging is modified to avoid writing passwords in cleartext for the following statements:

```
CREATE USER ... IDENTIFIED BY ...

GRANT ... IDENTIFIED BY ...

SET PASSWORD ...

SLAVE START ... PASSWORD = ... (as of 5.6.4)

CREATE SERVER ... OPTIONS(... PASSWORD ...) (as of 5.6.9)

ALTER SERVER ... OPTIONS(... PASSWORD ...) (as of 5.6.9)
```

Passwords in those statements are rewritten to not appear literally in statement text written to the general query log, slow query log, and binary log. Rewriting does not apply to other statements. In particular, INSERT or UPDATE statements for the mysql.user table that refer to literal passwords are logged as is, so you should avoid such statements. (Direct manipulation of grant tables is discouraged, anyway.)

For the general query log, password rewriting can be suppressed by starting the server with the --log-raw option. For security reasons, this option is not recommended for production use. For diagnostic purposes, it may be useful to see the exact text of statements as received by the server.

Contents of the audit log file produced by the audit log plugin are not encrypted. For security reasons, this file should be written to a directory accessible only to the MySQL server and users with a legitimate reason to view the log. See Section 6.3.2, "MySQL Enterprise Audit Security Considerations".

To guard log files against unwarranted exposure, locate them in a directory that restricts access to the server and the database administrator. If the server logs to tables in the mysql database, grant access to those tables only to the database administrator.

Replication slaves store the password for the replication master in the master info repository, which can be either a file or a table (see Replication Relay and Status Logs). Ensure that the repository can be accessed only by the database administrator. As of MySQL 5.6.4, an alternative to storing the password in a file is to use the START SLAVE statement to specify credentials for connecting to the master.

Use a restricted access mode to protect database backups that include log tables or log files containing passwords.

2.2.4 Password Hashing in MySQL

Note

The information in this section applies only for accounts that use the mysql_native_password or mysql_old_password authentication plugins.

MySQL lists user accounts in the user table of the mysql database. Each MySQL account can be assigned a password, although the user table does not store the cleartext version of the password, but a hash value computed from it.

MySQL uses passwords in two phases of client/server communication:

- When a client attempts to connect to the server, there is an initial authentication step in which the client must present a password that has a hash value matching the hash value stored in the user table for the account the client wants to use.
- After the client connects, it can (if it has sufficient privileges) set or change the password hash for accounts listed in the user table. The client can do this by using the PASSWORD() function to generate

a password hash, or by using a password-generating statement (CREATE USER, GRANT, or SET PASSWORD).

In other words, the server *checks* hash values during authentication when a client first attempts to connect. The server *generates* hash values if a connected client invokes the PASSWORD() function or uses a password-generating statement to set or change a password.

Password hashing methods in MySQL have the history described following. These changes are illustrated by changes in the result from the PASSWORD() function that computes password hash values and in the structure of the user table where passwords are stored.

The Original (Pre-4.1) Hashing Method

The original hashing method produced a 16-byte string. Such hashes look like this:

```
mysql> SELECT PASSWORD('mypass');
+-----+
| PASSWORD('mypass') |
+-----+
| 6f8c114b58f2ce9e |
+-----+
```

To store account passwords, the Password column of the user table was at this point 16 bytes long.

The 4.1 Hashing Method

MySQL 4.1 introduced password hashing that provided better security and reduced the risk of passwords being intercepted. There were several aspects to this change:

- Different format of password values produced by the PASSWORD() function
- Widening of the Password column
- · Control over the default hashing method
- · Control over the permitted hashing methods for clients attempting to connect to the server

The changes in MySQL 4.1 took place in two stages:

- MySQL 4.1.0 used a preliminary version of the 4.1 hashing method. This method was short lived and the following discussion says nothing more about it.
- In MySQL 4.1.1, the hashing method was modified to produce a longer 41-byte hash value:

The longer password hash format has better cryptographic properties, and client authentication based on long hashes is more secure than that based on the older short hashes.

To accommodate longer password hashes, the Password column in the user table was changed at this point to be 41 bytes, its current length.

A widened Password column can store password hashes in both the pre-4.1 and 4.1 formats. The format of any given hash value can be determined two ways:

- The length: 4.1 and pre-4.1 hashes are 41 and 16 bytes, respectively.
- Password hashes in the 4.1 format always begin with a "*" character, whereas passwords in the pre-4.1 format never do.

To permit explicit generation of pre-4.1 password hashes, two additional changes were made:

- The OLD_PASSWORD() function was added, which returns hash values in the 16-byte format.
- For compatibility purposes, the old_passwords system variable was added, to enable DBAs and applications control over the hashing method. The default old_passwords value of 0 causes hashing to use the 4.1 method (41-byte hash values), but setting old_passwords=1 causes hashing to use the pre-4.1 method. In this case, PASSWORD() produces 16-byte values and is equivalent to OLD_PASSWORD()

To permit DBAs control over how clients are permitted to connect, the secure_auth system variable
was added. Starting the server with this variable disabled or enabled permits or prohibits clients to
connect using the older pre-4.1 password hashing method. Before MySQL 5.6.5, secure_auth is
disabled by default. As of 5.6.5, secure_auth is enabled by default to promote a more secure default
configuration DBAs can disable it at their discretion, but this is not recommended, and pre-4.1 password
hashes are deprecated and should be avoided. (For account upgrade instructions, see Section 6.1.3,
"Migrating Away from Pre-4.1 Password Hashing and the mysql_old_password Plugin".)

In addition, the mysql client supports a --secure-auth option that is analogous to secure_auth, but from the client side. It can be used to prevent connections to less secure accounts that use pre-4.1 password hashing. This option is disabled by default before MySQL 5.6.7, enabled thereafter.

Compatibility Issues Related to Hashing Methods

The widening of the Password column in MySQL 4.1 from 16 bytes to 41 bytes affects installation or upgrade operations as follows:

- If you perform a new installation of MySQL, the Password column is made 41 bytes long automatically.
- Upgrades from MySQL 4.1 or later to current versions of MySQL should not give rise to any issues in regard to the Password column because both versions use the same column length and password hashing method.
- For upgrades from a pre-4.1 release to 4.1 or later, you must upgrade the system tables after upgrading. (See mysql_upgrade — Check and Upgrade MySQL Tables.)

The 4.1 hashing method is understood only by MySQL 4.1 (and higher) servers and clients, which can result in some compatibility problems. A 4.1 or higher client can connect to a pre-4.1 server, because the client understands both the pre-4.1 and 4.1 password hashing methods. However, a pre-4.1 client that attempts to connect to a 4.1 or higher server may run into difficulties. For example, a 4.0 mysql client may fail with the following error message:

```
shell> mysql -h localhost -u root
Client does not support authentication protocol requested
by server; consider upgrading MySQL client
```

This phenomenon also occurs for attempts to use the older PHP mysql extension after upgrading to MySQL 4.1 or higher. (See Common Problems with MySQL and PHP.)

The following discussion describes the differences between the pre-4.1 and 4.1 hashing methods, and what you should do if you upgrade your server but need to maintain backward compatibility with pre-4.1

clients. (However, permitting connections by old clients is not recommended and should be avoided if possible.) Additional information can be found in Client does not support authentication protocol. This information is of particular importance to PHP programmers migrating MySQL databases from versions older than 4.1 to 4.1 or higher.

The differences between short and long password hashes are relevant both for how the server uses passwords during authentication and for how it generates password hashes for connected clients that perform password-changing operations.

The way in which the server uses password hashes during authentication is affected by the width of the Password column:

- · If the column is short, only short-hash authentication is used.
- If the column is long, it can hold either short or long hashes, and the server can use either format:
 - Pre-4.1 clients can connect, but because they know only about the pre-4.1 hashing method, they can authenticate only using accounts that have short hashes.
 - 4.1 and later clients can authenticate using accounts that have short or long hashes.

Even for short-hash accounts, the authentication process is actually a bit more secure for 4.1 and later clients than for older clients. In terms of security, the gradient from least to most secure is:

- Pre-4.1 client authenticating with short password hash
- 4.1 or later client authenticating with short password hash
- 4.1 or later client authenticating with long password hash

The way in which the server generates password hashes for connected clients is affected by the width of the Password column and by the old_passwords system variable. A 4.1 or later server generates long hashes only if certain conditions are met: The Password column must be wide enough to hold long values and old passwords must not be set to 1.

Those conditions apply as follows:

- The Password column must be wide enough to hold long hashes (41 bytes). If the column has not been updated and still has the pre-4.1 width of 16 bytes, the server notices that long hashes cannot fit into it and generates only short hashes when a client performs password-changing operations using the Password() function or a password-generating statement. This is the behavior that occurs if you have upgraded from a version of MySQL older than 4.1 to 4.1 or later but have not yet run the mysql_upgrade program to widen the Password column.
- If the Password column is wide, it can store either short or long password hashes. In this case, the PASSWORD() function and password-generating statements generate long hashes unless the server was started with the old_passwords system variable set to 1 to force the server to generate short password hashes instead.

The purpose of the old_passwords system variable is to permit backward compatibility with pre-4.1 clients under circumstances where the server would otherwise generate long password hashes. The option does not affect authentication (4.1 and later clients can still use accounts that have long password hashes), but it does prevent creation of a long password hash in the user table as the result of a password-changing operation. Were that permitted to occur, the account could no longer be used by pre-4.1 clients. With old_passwords disabled, the following undesirable scenario is possible:

An old pre-4.1 client connects to an account that has a short password hash.

- The client changes its own password. With old_passwords disabled, this results in the account having a long password hash.
- The next time the old client attempts to connect to the account, it cannot, because the account has a long password hash that requires the 4.1 hashing method during authentication. (Once an account has a long password hash in the user table, only 4.1 and later clients can authenticate for it because pre-4.1 clients do not understand long hashes.)

This scenario illustrates that, if you must support older pre-4.1 clients, it is problematic to run a 4.1 or higher server without old_passwords set to 1. By running the server with old_passwords=1, password-changing operations do not generate long password hashes and thus do not cause accounts to become inaccessible to older clients. (Those clients cannot inadvertently lock themselves out by changing their password and ending up with a long password hash.)

The downside of old_passwords=1 is that any passwords created or changed use short hashes, even for 4.1 or later clients. Thus, you lose the additional security provided by long password hashes. To create an account that has a long hash (for example, for use by 4.1 clients) or to change an existing account to use a long password hash, an administrator can set the session value of old_passwords set to 0 while leaving the global value set to 1:

The following scenarios are possible in MySQL 4.1 or later. The factors are whether the Password column is short or long, and, if long, whether the server is started with old_passwords enabled or disabled.

Scenario 1: Short Password column in user table:

- Only short hashes can be stored in the Password column.
- The server uses only short hashes during client authentication.
- For connected clients, password hash-generating operations involving the PASSWORD() function or password-generating statements use short hashes exclusively. Any change to an account's password results in that account having a short password hash.
- The value of old_passwords is irrelevant because with a short Password column, the server generates only short password hashes anyway.

This scenario occurs when a pre-4.1 MySQL installation has been upgraded to 4.1 or later but mysql_upgrade has not been run to upgrade the system tables in the mysql database. (This is not a recommended configuration because it does not permit use of more secure 4.1 password hashing.)

Scenario 2: Long Password column; server started with old_passwords=1:

- Short or long hashes can be stored in the Password column.
- 4.1 and later clients can authenticate for accounts that have short or long hashes.

- Pre-4.1 clients can authenticate only for accounts that have short hashes.
- For connected clients, password hash-generating operations involving the PASSWORD() function or password-generating statements use short hashes exclusively. Any change to an account's password results in that account having a short password hash.

In this scenario, newly created accounts have short password hashes because old_passwords=1 prevents generation of long hashes. Also, if you create an account with a long hash before setting old_passwords to 1, changing the account's password while old_passwords=1 results in the account being given a short password, causing it to lose the security benefits of a longer hash.

To create a new account that has a long password hash, or to change the password of any existing account to use a long hash, first set the session value of old_passwords set to 0 while leaving the global value set to 1, as described previously.

In this scenario, the server has an up to date Password column, but is running with the default password hashing method set to generate pre-4.1 hash values. This is not a recommended configuration but may be useful during a transitional period in which pre-4.1 clients and passwords are upgraded to 4.1 or later. When that has been done, it is preferable to run the server with old_passwords=0 and secure_auth=1.

Scenario 3: Long Password column; server started with old_passwords=0:

- Short or long hashes can be stored in the Password column.
- 4.1 and later clients can authenticate using accounts that have short or long hashes.
- Pre-4.1 clients can authenticate only using accounts that have short hashes.
- For connected clients, password hash-generating operations involving the PASSWORD() function or
 password-generating statements use long hashes exclusively. A change to an account's password
 results in that account having a long password hash.

As indicated earlier, a danger in this scenario is that it is possible for accounts that have a short password hash to become inaccessible to pre-4.1 clients. A change to such an account's password made using the PASSWORD() function or a password-generating statement results in the account being given a long password hash. From that point on, no pre-4.1 client can connect to the server using that account. The client must upgrade to 4.1 or later.

If this is a problem, you can change a password in a special way. For example, normally you use SET PASSWORD as follows to change an account password:

```
SET PASSWORD FOR 'some_user'@'some_host' = PASSWORD('mypass');
```

To change the password but create a short hash, use the OLD_PASSWORD() function instead:

```
SET PASSWORD FOR 'some_user'@'some_host' = OLD_PASSWORD('mypass');
```

OLD_PASSWORD() is useful for situations in which you explicitly want to generate a short hash.

The disadvantages for each of the preceding scenarios may be summarized as follows:

In scenario 1, you cannot take advantage of longer hashes that provide more secure authentication.

In scenario 2, old_passwords=1 prevents accounts with short hashes from becoming inaccessible, but password-changing operations cause accounts with long hashes to revert to short hashes unless you take care to change the session value of old_passwords to 0 first.

In scenario 3, accounts with short hashes become inaccessible to pre-4.1 clients if you change their passwords without explicitly using OLD PASSWORD().

The best way to avoid compatibility problems related to short password hashes is to not use them:

- Upgrade all client programs to MySQL 4.1 or later.
- Run the server with old_passwords=0.
- Reset the password for any account with a short password hash to use a long password hash.
- For additional security, run the server with secure_auth=1.

2.2.5 Implications of Password Hashing Changes in MySQL 4.1 for Application Programs

An upgrade to MySQL version 4.1 or later can cause compatibility issues for applications that use PASSWORD() to generate passwords for their own purposes. Applications really should not do this, because PASSWORD() should be used only to manage passwords for MySQL accounts. But some applications use PASSWORD() for their own purposes anyway.

If you upgrade to 4.1 or later from a pre-4.1 version of MySQL and run the server under conditions where it generates long password hashes, an application using PASSWORD() for its own passwords breaks. The recommended course of action in such cases is to modify the application to use another function, such as SHA2(), SHA1(), or MD5(), to produce hashed values. If that is not possible, you can use the OLD_PASSWORD() function, which is provided for generate short hashes in the old format. However, you should note that OLD PASSWORD() may one day no longer be supported.

If the server is running with old_passwords=1, it generates short hashes and OLD_PASSWORD() is equivalent to PASSWORD().

PHP programmers migrating their MySQL databases from version 4.0 or lower to version 4.1 or higher should see MySQL and PHP.

2.3 Making MySQL Secure Against Attackers

When you connect to a MySQL server, you should use a password. The password is not transmitted in clear text over the connection. Password handling during the client connection sequence was upgraded in MySQL 4.1.1 to be very secure. If you are still using pre-4.1.1-style passwords, the encryption algorithm is not as strong as the newer algorithm. With some effort, a clever attacker who can sniff the traffic between the client and the server can crack the password. (See Section 2.2.4, "Password Hashing in MySQL", for a discussion of the different password handling methods.)

All other information is transferred as text, and can be read by anyone who is able to watch the connection. If the connection between the client and the server goes through an untrusted network, and you are concerned about this, you can use the compressed protocol to make traffic much more difficult to decipher. You can also use MySQL's internal SSL support to make the connection even more secure. See Section 5.9, "Using Secure Connections". Alternatively, use SSH to get an encrypted TCP/IP connection between a MySQL server and a MySQL client. You can find an Open Source SSH client at http://www.openssh.org/, and a comparison of both Open Source and Commercial SSH clients at http://en.wikipedia.org/wiki/Comparison_of_SSH_clients.

To make a MySQL system secure, you should strongly consider the following suggestions:

 Require all MySQL accounts to have a password. A client program does not necessarily know the identity of the person running it. It is common for client/server applications that the user can specify any user name to the client program. For example, anyone can use the <code>mysql</code> program to connect as any other person simply by invoking it as <code>mysql</code> -u <code>other_user</code> db_name if <code>other_user</code> has no password. If all accounts have a password, connecting using another user's account becomes much more difficult.

For a discussion of methods for setting passwords, see Section 5.5, "Assigning Account Passwords".

- Make sure that the only Unix user account with read or write privileges in the database directories is the
 account that is used for running mysgld.

mysqld can (and should) be run as an ordinary, unprivileged user instead. You can create a separate Unix account named mysql to make everything even more secure. Use this account only for administering MySQL. To start mysqld as a different Unix user, add a user option that specifies the user name in the [mysqld] group of the my.cnf option file where you specify server options. For example:

```
[mysqld]
user=mysql
```

This causes the server to start as the designated user whether you start it manually or by using mysqld_safe or mysql.server. For more details, see Section 2.5, "How to Run MySQL as a Normal User".

Running mysqld as a Unix user other than root does not mean that you need to change the root user name in the user table. User names for MySQL accounts have nothing to do with user names for Unix accounts.

• Do not grant the FILE privilege to nonadministrative users. Any user that has this privilege can write a file anywhere in the file system with the privileges of the mysqld daemon. This includes the server's data directory containing the files that implement the privilege tables. To make FILE-privilege operations a bit safer, files generated with SELECT ... INTO OUTFILE do not overwrite existing files and are writable by everyone.

The FILE privilege may also be used to read any file that is world-readable or accessible to the Unix user that the server runs as. With this privilege, you can read any file into a database table. This could be abused, for example, by using LOAD DATA to load /etc/passwd into a table, which then can be displayed with SELECT.

To limit the location in which files can be read and written, set the secure_file_priv system to a specific directory. See Server System Variables.

• Do not grant the PROCESS or SUPER privilege to nonadministrative users. The output of mysqladmin processlist and SHOW PROCESSLIST shows the text of any statements currently being executed, so any user who is permitted to see the server process list might be able to see statements issued by other users such as UPDATE user SET password=PASSWORD('not_secure').

mysqld reserves an extra connection for users who have the SUPER privilege, so that a MySQL root user can log in and check server activity even if all normal connections are in use.

The SUPER privilege can be used to terminate client connections, change server operation by changing the value of system variables, and control replication servers.

- Do not permit the use of symlinks to tables. (This capability can be disabled with the --skip-symbolic-links option.) This is especially important if you run mysqld as root, because anyone that has write access to the server's data directory then could delete any file in the system! See Using Symbolic Links for MylSAM Tables on Unix.
- Stored programs and views should be written using the security guidelines discussed in Access Control for Stored Programs and Views.
- If you do not trust your DNS, you should use IP addresses rather than host names in the grant tables. In any case, you should be very careful about creating grant table entries using host name values that contain wildcards.
- If you want to restrict the number of connections permitted to a single account, you can do so by setting the max_user_connections variable in mysqld. The GRANT statement also supports resource control options for limiting the extent of server use permitted to an account. See GRANT Syntax.
- If the plugin directory is writable by the server, it may be possible for a user to write executable code to a file in the directory using SELECT ... INTO DUMPFILE. This can be prevented by making plugin_dir read only to the server or by setting --secure-file-priv to a directory where SELECT writes can be made safely.

2.4 Security-Related mysqld Options and Variables

The following table shows mysqld options and system variables that affect security. For descriptions of each of these, see Server Command Options, and Server System Variables.

Table 2.1 Security Option/Variable Summary

Name	Cmd-Line	Option File	System Var	Status Var	Var Scope	Dynamic
allow-suspicious- udfs	Yes	Yes				
automatic_sp_privi	leges		Yes		Global	Yes
chroot	Yes	Yes				
des-key-file	Yes	Yes				
local_infile			Yes		Global	Yes
old_passwords			Yes		Both	Yes
safe-user-create	Yes	Yes				
secure-auth	Yes	Yes			Global	Yes
- Variable: secure_auth			Yes		Global	Yes
secure-file-priv	Yes	Yes			Global	No
- Variable: secure_file_priv			Yes		Global	No
skip-grant-tables	Yes	Yes				
skip-name-resolve	Yes	Yes			Global	No
- Variable: skip_name_resolve	₹		Yes		Global	No
skip-networking	Yes	Yes			Global	No
Variable: skip_networking			Yes		Global	No

Name	Cmd-Line	Option File	System Var	Status Var	Var Scope	Dynamic
skip-show- database	Yes	Yes			Global	No
- Variable: skip_show_databa	se		Yes		Global	No

2.5 How to Run MySQL as a Normal User

On Windows, you can run the server as a Windows service using a normal user account.

On Linux, for installations performed using a MySQL repository, RPM packages, or Debian packages, the MySQL server mysqld should be started by the local mysql operating system user. Starting by another operating system user is not supported by the init scripts that are included as part of the installation.

On Unix (or Linux for installations performed using tar or tar.gz packages), the MySQL server mysqld can be started and run by any user. However, you should avoid running the server as the Unix root user for security reasons. To change mysqld to run as a normal unprivileged Unix user $user_name$, you must do the following:

- 1. Stop the server if it is running (use mysgladmin shutdown).
- 2. Change the database directories and files so that *user_name* has privileges to read and write files in them (you might need to do this as the Unix root user):

```
shell> chown -R user_name /path/to/mysql/datadir
```

If you do not do this, the server will not be able to access databases or tables when it runs as $user_name$.

If directories or files within the MySQL data directory are symbolic links, chown -R might not follow symbolic links for you. If it does not, you will also need to follow those links and change the directories and files they point to.

- 3. Start the server as user <u>user_name</u>. Another alternative is to start <u>mysqld</u> as the Unix <u>root</u> user and use the <u>--user=user_name</u> option. <u>mysqld</u> starts up, then switches to run as the Unix user <u>user name</u> before accepting any connections.
- 4. To start the server as the given user automatically at system startup time, specify the user name by adding a user option to the [mysqld] group of the /etc/my.cnf option file or the my.cnf option file in the server's data directory. For example:

```
[mysqld]
user=user_name
```

If your Unix machine itself is not secured, you should assign passwords to the MySQL root accounts in the grant tables. Otherwise, any user with a login account on that machine can run the mysql client with a --user=root option and perform any operation. (It is a good idea to assign passwords to MySQL accounts in any case, but especially so when other login accounts exist on the server host.) See Section 3.4, "Securing the Initial MySQL Accounts".

2.6 Security Issues with LOAD DATA LOCAL

The LOAD DATA statement can load a file that is located on the server host, or it can load a file that is located on the client host when the LOCAL keyword is specified.

There are two potential security issues with supporting the LOCAL version of LOAD DATA statements:

- The transfer of the file from the client host to the server host is initiated by the MySQL server. In theory,
 a patched server could be built that would tell the client program to transfer a file of the server's choosing
 rather than the file named by the client in the LOAD DATA statement. Such a server could access any file
 on the client host to which the client user has read access.
- In a Web environment where the clients are connecting from a Web server, a user could use LOAD
 DATA LOCAL to read any files that the Web server process has read access to (assuming that a user
 could run any command against the SQL server). In this environment, the client with respect to the
 MySQL server actually is the Web server, not the remote program being run by the user who connects to
 the Web server.

To deal with these problems, LOAD DATA LOCAL works like this:

- By default, all MySQL clients and libraries in binary distributions are compiled with the DENABLED_LOCAL_INFILE=1 option.
- If you build MySQL from source but do not invoke CMake with the -DENABLED_LOCAL_INFILE=1 option, LOAD DATA LOCAL cannot be used by any client unless it is written explicitly to invoke mysql_options(... MYSQL_OPT_LOCAL_INFILE, 0). See mysql_options().
- You can disable all LOAD DATA LOCAL statements from the server side by starting mysqld with the -- local-infile=0 option.
- For the mysql command-line client, enable LOAD DATA LOCAL by specifying the --local-infile[=1] option, or disable it with the --local-infile=0 option. For mysqlimport, local data file loading is off by default; enable it with the --local or -L option. In any case, successful use of a local load operation requires that the server permits it.
- If you use LOAD DATA LOCAL in Perl scripts or other programs that read the [client] group from option files, you can add the local-infile=1 option to that group. However, to keep this from causing problems for programs that do not understand local-infile, specify it using the loose- prefix:

```
[client]
loose-local-infile=1
```

• If LOAD DATA LOCAL is disabled, either in the server or the client, a client that attempts to issue such a statement receives the following error message:

```
ERROR 1148: The used command is not allowed with this MySQL version
```

2.7 Client Programming Security Guidelines

Applications that access MySQL should not trust any data entered by users, who can try to trick your code by entering special or escaped character sequences in Web forms, URLs, or whatever application you have built. Be sure that your application remains secure if a user enters something like "; DROP DATABASE mysql;". This is an extreme example, but large security leaks and data loss might occur as a result of hackers using similar techniques, if you do not prepare for them.

A common mistake is to protect only string data values. Remember to check numeric data as well. If an application generates a query such as SELECT * FROM table WHERE ID=234 when a user enters the value 234, the user can enter the value 234 OR 1=1 to cause the application to generate the query SELECT * FROM table WHERE ID=234 OR 1=1. As a result, the server retrieves every row in the table. This exposes every row and causes excessive server load. The simplest way to protect from

this type of attack is to use single quotation marks around the numeric constants: SELECT * FROM table WHERE ID='234'. If the user enters extra information, it all becomes part of the string. In a numeric context, MySQL automatically converts this string to a number and strips any trailing nonnumeric characters from it.

Sometimes people think that if a database contains only publicly available data, it need not be protected. This is incorrect. Even if it is permissible to display any row in the database, you should still protect against denial of service attacks (for example, those that are based on the technique in the preceding paragraph that causes the server to waste resources). Otherwise, your server becomes unresponsive to legitimate users.

Checklist:

- Enable strict SQL mode to tell the server to be more restrictive of what data values it accepts. See Server SQL Modes.
- Try to enter single and double quotation marks ("1" and """) in all of your Web forms. If you get any kind of MySQL error, investigate the problem right away.
- Try to modify dynamic URLs by adding \$22 ("""), \$23 ("#"), and \$27 ("'") to them.
- Try to modify data types in dynamic URLs from numeric to character types using the characters shown in the previous examples. Your application should be safe against these and similar attacks.
- Try to enter characters, spaces, and special symbols rather than numbers in numeric fields. Your
 application should remove them before passing them to MySQL or else generate an error. Passing
 unchecked values to MySQL is very dangerous!
- Check the size of data before passing it to MySQL.
- Have your application connect to the database using a user name different from the one you use for administrative purposes. Do not give your applications any access privileges they do not need.

Many application programming interfaces provide a means of escaping special characters in data values. Properly used, this prevents application users from entering values that cause the application to generate statements that have a different effect than you intend:

- MySQL C API: Use the mysql real escape string() API call.
- MySQL++: Use the escape and quote modifiers for query streams.
- PHP: Use either the <code>mysqli</code> or <code>pdo_mysql</code> extensions, and not the older <code>ext/mysql</code> extension. The preferred API's support the improved MySQL authentication protocol and passwords, as well as prepared statements with placeholders. See also Choosing an API.

If the older <code>ext/mysql</code> extension must be used, then for escaping use the <code>mysql_real_escape_string()</code> function and not <code>mysql_escape_string()</code> or <code>addslashes()</code> because only <code>mysql_real_escape_string()</code> is character set-aware; the other functions can be "bypassed" when using (invalid) multibyte character sets.

- Perl DBI: Use placeholders or the quote() method.
- Ruby DBI: Use placeholders or the quote() method.
- Java JDBC: Use a PreparedStatement object and placeholders.

Other programming interfaces might have similar capabilities.

Chapter 3 Postinstallation Setup and Testing

Table of Contents

3.1 Initializing the Data Directory	19
3.1.1 Problems Running mysql_install_db	21
3.2 Starting the Server	
3.2.1 Troubleshooting Problems Starting the MySQL Server	
3.3 Testing the Server	26
3.4 Securing the Initial MySQL Accounts	
3.5 Starting and Stopping MySQL Automatically	32

This section discusses tasks that you should perform after installing MySQL:

- If necessary, initialize the data directory and create the MySQL grant tables. For some MySQL installation methods, data directory initialization may be done for you automatically:
 - · Installation on Windows
 - Installation on Linux using a server RPM or Debian distribution from Oracle.
 - Installation using the native packaging system on many platforms, including Debian Linux, Ubuntu Linux, Gentoo Linux, and others.
 - Installation on OS X using a DMG distribution.

For other platforms and installation types, including installation from generic binary and source distributions, you must initialize the data directory yourself. For instructions, see Section 3.1, "Initializing the Data Directory".

- For instructions, see Section 3.2, "Starting the Server", and Section 3.3, "Testing the Server".
- Assign passwords to any initial accounts in the grant tables, if that was not already done during data directory initialization. Passwords prevent unauthorized access to the MySQL server. You may also wish to restrict access to test databases. For instructions, see Section 3.4, "Securing the Initial MySQL Accounts".
- Optionally, arrange for the server to start and stop automatically when your system starts and stops. For instructions, see Section 3.5, "Starting and Stopping MySQL Automatically".
- Optionally, populate time zone tables to enable recognition of named time zones. For instructions, see MySQL Server Time Zone Support.

When you are ready to create additional user accounts, you can find information on the MySQL access control system and account management in Chapter 4, *The MySQL Access Privilege System*, and Chapter 5, *MySQL User Account Management*.

3.1 Initializing the Data Directory

After installing MySQL, you must initialize the data directory, including the tables in the mysql system database. For some MySQL installation methods, data directory initialization may be done automatically,

as described in Chapter 3, *Postinstallation Setup and Testing*. For other installation methods, including installation from generic binary and source distributions, you must initialize the data directory yourself.

This section describes how to initialize the data directory on Unix and Unix-like systems. (For Windows, see Windows Postinstallation Procedures.) For some suggested commands that you can use to test whether the server is accessible and working properly, see Section 3.3, "Testing the Server".

In the examples shown here, the server runs under the user ID of the ${\tt mysql}$ login account. This assumes that such an account exists. Either create the account if it does not exist, or substitute the name of a different existing login account that you plan to use for running the server. For information about creating the account, see Creating a ${\tt mysql}$ System User and Group, in Installing MySQL on Unix/Linux Using Generic Binaries.

1. Change location into the top-level directory of your MySQL installation, represented here by BASEDIR:

```
shell> cd BASEDIR
```

BASEDIR is likely to be something like /usr/local/mysql, /usr/local, or /usr/bin (for installation with MySQL Yum repository, or other means). The following steps assume that you have changed location to this directory.

You will find several files and subdirectories in the <code>BASEDIR</code> directory. The most important for installation purposes are the <code>bin</code> and <code>scripts</code> subdirectories, which contain the server as well as client and utility programs.

2. If necessary, ensure that the distribution contents are accessible to mysql. If you installed the distribution as mysql, no further action is required. If you installed the distribution as root, its contents will be owned by root. Change its ownership to mysql by executing the following commands as root in the installation directory. The first command changes the owner attribute of the files to the mysql user. The second changes the group attribute to the mysql group.

```
shell> chown -R mysql .
shell> chgrp -R mysql .
```

3. If necessary, initialize the data directory, including the mysql database containing the initial MySQL grant tables that determine how users are permitted to connect to the server.

Typically, data directory initialization need be done only the first time you install MySQL. If you are upgrading an existing installation, you should run mysql_upgrade instead (see mysql_upgrade — Check and Upgrade MySQL Tables). However, the command that initializes the data directory does not overwrite any existing privilege tables, so it should be safe to run in any circumstances.

```
shell> scripts/mysql_install_db --user=mysql
```

It is important to make sure that the database directories and files are owned by the mysql login account so that the server has read and write access to them when you run it later. To ensure this if you run mysql_install_db as root, include the --user option as shown. Otherwise, you should execute the program while logged in as mysql, in which case you can omit the --user option from the command.

The mysql_install_db command creates the server's data directory. Under the data directory, it creates directories for the mysql database that holds the grant tables and the test database that you can use to test MySQL. The program also creates privilege table entries for the initial account or accounts. test_. For a complete listing and description of the grant tables, see Chapter 4, The MySQL Access Privilege System.

It might be necessary to specify other options such as --basedir or --datadir if mysql_install_db does not identify the correct locations for the installation directory or data directory. For example:

```
shell> scripts/mysql_install_db --user=mysql \
     --basedir=/opt/mysql/mysql \
     --datadir=/opt/mysql/mysql/data
```

For a more secure installation, invoke <code>mysql_install_db</code> with the <code>--random-passwords</code> option. This causes it to assign a random password to the MySQL <code>root</code> accounts, set the "password expired" flag for those accounts, and remove the anonymous-user MySQL accounts. For additional details, see <code>mysql_install_db</code> — Initialize MySQL Data Directory. (Install operations using RPMs for Unbreakable Linux Network are unaffected because they do not use <code>mysql_install_db</code>.)

If you do not want to have the test database, you can remove it after starting the server, using the instructions in Section 3.4, "Securing the Initial MySQL Accounts".

If you have trouble with mysql_install_db at this point, see Section 3.1.1, "Problems Running mysql_install_db".

4. After initializing the data directory, you can establish the final installation ownership settings. To leave the installation owned by mysql, no action is required here. Otherwise, most of the MySQL installation can be owned by root if you like. The exception is that the data directory must be owned by mysql. To accomplish this, run the following commands as root in the installation directory. For some distribution types, the data directory might be named var rather than data; adjust the second command accordingly.

```
shell> chown -R root .
shell> chown -R mysql data
```

If the plugin directory (the directory named by the <code>plugin_dir</code> system variable) is writable by the server, it may be possible for a user to write executable code to a file in the directory using <code>SELECT ... INTO DUMPFILE</code>. This can be prevented by making the plugin directory read only to the server or by setting the <code>secure_file_priv</code> system variable at server startup to a directory where <code>SELECT</code> writes can be performed safely.

- 5. To specify options that the MySQL server should use at startup, put them in a /etc/my.cnf or /etc/mysql/my.cnf file. See Server Configuration Defaults. If you do not do this, the server starts with its default settings.
- 6. If you want MySQL to start automatically when you boot your machine, see Section 3.5, "Starting and Stopping MySQL Automatically".

Data directory initialization creates time zone tables in the mysql database but does not populate them. To do so, use the instructions in MySQL Server Time Zone Support.

3.1.1 Problems Running mysql_install_db

The purpose of the <code>mysql_install_db</code> program is to initialize the data directory, including the tables in the <code>mysql</code> system database. It does not overwrite existing MySQL privilege tables, and it does not affect any other data.

To re-create your privilege tables, first stop the <code>mysqld</code> server if it is running. Then rename the <code>mysql</code> directory under the data directory to save it, and run <code>mysql_install_db</code>. Suppose that your current directory is the <code>MySQL</code> installation directory and that <code>mysql_install_db</code> is located in the <code>bin</code> directory.

and the data directory is named data. To rename the mysql database and re-run $mysql_install_db$, use these commands.

```
shell> mv data/mysql data/mysql.old
shell> scripts/mysql_install_db --user=mysql
```

When you run mysql_install_db, you might encounter the following problems:

• mysql_install_db fails to install the grant tables

You may find that mysql_install_db fails to install the grant tables and terminates after displaying the following messages:

```
Starting mysqld daemon with databases from XXXXXXX
mysqld ended
```

In this case, you should examine the error log file very carefully. The log should be located in the directory XXXXXX named by the error message and should indicate why mysqld did not start. If you do not understand what happened, include the log when you post a bug report. See How to Report Bugs or Problems.

• There is a mysqld process running

This indicates that the server is running, in which case the grant tables have probably been created already. If so, there is no need to run mysql_install_db at all because it needs to be run only once, when you first install MySQL.

Installing a second mysqld server does not work when one server is running

This can happen when you have an existing MySQL installation, but want to put a new installation in a different location. For example, you might have a production installation, but you want to create a second installation for testing purposes. Generally the problem that occurs when you try to run a second server is that it tries to use a network interface that is in use by the first server. In this case, you should see one of the following error messages:

```
Can't start server: Bind on TCP/IP port:
Address already in use
Can't start server: Bind on unix socket...
```

For instructions on setting up multiple servers, see Running Multiple MySQL Instances on One Machine.

You do not have write access to the /tmp directory

If you do not have write access to create temporary files or a Unix socket file in the default location (the /tmp directory) or the TMPDIR environment variable, if it has been set, an error occurs when you run mysql_install_db or the mysqld server.

You can specify different locations for the temporary directory and Unix socket file by executing these commands prior to starting mysql_install_db or mysqld, where some_tmp_dir is the full path name to some directory for which you have write permission:

```
shell> TMPDIR=/some_tmp_dir/
shell> MYSQL_UNIX_PORT=/some_tmp_dir/mysql.sock
shell> export TMPDIR MYSQL_UNIX_PORT
```

Then you should be able to run mysql install db and start the server with these commands:

```
shell> scripts/mysql_install_db --user=mysql
shell> bin/mysqld_safe --user=mysql &
```

If mysql_install_db is located in the scripts directory, modify the first command to scripts/mysql_install_db.

See How to Protect or Change the MySQL Unix Socket File, and Environment Variables.

There are some alternatives to running the mysql_install_db program provided in the MySQL distribution:

• If you want the initial privileges to be different from the standard defaults, use account-management statements such as CREATE USER, GRANT, and REVOKE to change the privileges after the grant tables have been set up. In other words, run mysql_install_db, and then use mysql -u root mysql to connect to the server as the MySQL root user so that you can issue the necessary statements. (See Account Management Statements.)

To install MySQL on several machines with the same privileges, put the CREATE USER, GRANT, and REVOKE statements in a file and execute the file as a script using mysql after running mysql_install_db. For example:

```
shell> scripts/mysql_install_db --user=mysql
shell> bin/mysql -u root < your_script_file</pre>
```

This enables you to avoid issuing the statements manually on each machine.

• It is possible to re-create the grant tables completely after they have previously been created. You might want to do this if you are just learning how to use CREATE USER, GRANT, and REVOKE and have made so many modifications after running mysql_install_db that you want to wipe out the tables and start over.

To re-create the grant tables, stop the server if it is running and remove the mysql database directory. Then run mysql_install_db again.

3.2 Starting the Server

This section describes how start the server on Unix and Unix-like systems. (For Windows, see Starting the Server for the First Time.) For some suggested commands that you can use to test whether the server is accessible and working properly, see Section 3.3, "Testing the Server".

Start the MySQL server like this:

```
shell> bin/mysqld_safe --user=mysql &
```

It is important that the MySQL server be run using an unprivileged (non-root) login account. To ensure this if you run mysqld_safe as root, include the --user option as shown. Otherwise, execute the program while logged in as mysql, in which case you can omit the --user option from the command.

For further instructions for running MySQL as an unprivileged user, see Section 2.5, "How to Run MySQL as a Normal User".

If the command fails immediately and prints mysqld ended, look for information in the error log (which by default is the $host_name.err$ file in the data directory).

If the server is unable to access the data directory it starts or read the grant tables in the mysql database, it writes a message to its error log. Such problems can occur if you neglected to create the grant tables by initializing the data directory before proceeding to this step, or if you ran the command that initializes the data directory without the --user option. Remove the data directory and run the command with the --user option.

If you have other problems starting the server, see Section 3.2.1, "Troubleshooting Problems Starting the MySQL Server". For more information about $mysqld_safe$, see $mysqld_safe$ — MySQL Server Startup Script.

3.2.1 Troubleshooting Problems Starting the MySQL Server

This section provides troubleshooting suggestions for problems starting the server. For additional suggestions for Windows systems, see Troubleshooting a Microsoft Windows MySQL Server Installation.

If you have problems starting the server, here are some things to try:

• Check the error log to see why the server does not start. Log files are located in the data directory (typically C:\Program Files\MySQL\MySQL Server 5.6\data on Windows, /usr/local/mysql/data for a Unix/Linux binary distribution, and /usr/local/var for a Unix/Linux source distribution). Look in the data directory for files with names of the form host_name.err and host_name.log, where host_name is the name of your server host. Then examine the last few lines of these files. Use tail to display them:

```
shell> tail host_name.err
shell> tail host_name.log
```

• Specify any special options needed by the storage engines you are using. You can create a my.cnf file and specify startup options for the engines that you plan to use. If you are going to use storage engines that support transactional tables (InnoDB, NDB), be sure that you have them configured the way you want before starting the server. If you are using InnoDB tables, see InnoDB Configuration for guidelines and InnoDB Startup Options and System Variables for option syntax.

Although storage engines use default values for options that you omit, Oracle recommends that you review the available options and specify explicit values for any options whose defaults are not appropriate for your installation.

• Make sure that the server knows where to find the data directory. The mysqld server uses this directory as its current directory. This is where it expects to find databases and where it expects to write log files. The server also writes the pid (process ID) file in the data directory.

The default data directory location is hardcoded when the server is compiled. To determine what the default path settings are, invoke <code>mysqld</code> with the <code>--verbose</code> and <code>--help</code> options. If the data directory is located somewhere else on your system, specify that location with the <code>--datadir</code> option to <code>mysqld</code> or <code>mysqld_safe</code>, on the command line or in an option file. Otherwise, the server will not work properly. As an alternative to the <code>--datadir</code> option, you can specify <code>mysqld</code> the location of the base directory under which <code>MySQL</code> is installed with the <code>--basedir</code>, and <code>mysqld</code> looks for the <code>data</code> directory there.

To check the effect of specifying path options, invoke <code>mysqld</code> with those options followed by the <code>--verbose</code> and <code>--help</code> options. For example, if you change location into the directory where <code>mysqld</code> is installed and then run the following command, it shows the effect of starting the server with a base directory of <code>/usr/local</code>:

```
shell> ./mysqld --basedir=/usr/local --verbose --help
```

You can specify other options such as --datadir as well, but --verbose and --help must be the last options.

Once you determine the path settings you want, start the server without --verbose and --help.

If mysqld is currently running, you can find out what path settings it is using by executing this command:

```
shell> mysqladmin variables
```

Or:

```
shell> mysqladmin -h host_name variables
```

host_name is the name of the MySQL server host.

• Make sure that the server can access the data directory. The ownership and permissions of the data directory and its contents must allow the server to read and modify them.

If you get Errcode 13 (which means Permission denied) when starting mysqld, this means that the privileges of the data directory or its contents do not permit server access. In this case, you change the permissions for the involved files and directories so that the server has the right to use them. You can also start the server as root, but this raises security issues and should be avoided.

Change location into the data directory and check the ownership of the data directory and its contents to make sure the server has access. For example, if the data directory is /usr/local/mysql/var, use this command:

```
shell> ls -la /usr/local/mysql/var
```

If the data directory or its files or subdirectories are not owned by the login account that you use for running the server, change their ownership to that account. If the account is named mysql, use these commands:

```
shell> chown -R mysql /usr/local/mysql/var
shell> chgrp -R mysql /usr/local/mysql/var
```

Even with correct ownership, MySQL might fail to start up if there is other security software running on your system that manages application access to various parts of the file system. In this case, reconfigure that software to enable mysqld to access the directories it uses during normal operation.

Verify that the network interfaces the server wants to use are available.

If either of the following errors occur, it means that some other program (perhaps another mysqld server) is using the TCP/IP port or Unix socket file that mysqld is trying to use:

```
Can't start server: Bind on TCP/IP port: Address already in use
Can't start server: Bind on unix socket...
```

Use ps to determine whether you have another mysqld server running. If so, shut down the server before starting mysqld again. (If another server is running, and you really want to run multiple servers, you can find information about how to do so in Running Multiple MySQL Instances on One Machine.)

If no other server is running, execute the command telnet <code>your_host_name</code> <code>tcp_ip_port_number</code>. (The default MySQL port number is 3306.) Then press Enter a couple of times. If you do not get an error message like telnet: Unable to connect to remote host: Connection refused, some other program is using the TCP/IP port that <code>mysqld</code> is trying to use. Track down what program this is and disable it, or tell <code>mysqld</code> to listen to a different port with the <code>--port</code> option. In this case, specify the same non-default port number for client programs when connecting to the server using TCP/IP.

Another reason the port might be inaccessible is that you have a firewall running that blocks connections to it. If so, modify the firewall settings to permit access to the port.

If the server starts but you cannot connect to it, make sure that you have an entry in /etc/hosts that looks like this:

```
127.0.0.1 localhost
```

If you cannot get mysqld to start, try to make a trace file to find the problem by using the --debug option. See The DBUG Package.

3.3 Testing the Server

After the data directory is initialized and you have started the server, perform some simple tests to make sure that it works satisfactorily. This section assumes that your current location is the MySQL installation directory and that it has a bin subdirectory containing the MySQL programs used here. If that is not true, adjust the command path names accordingly.

Alternatively, add the bin directory to your PATH environment variable setting. That enables your shell (command interpreter) to find MySQL programs properly, so that you can run a program by typing only its name, not its path name. See Setting Environment Variables.

Use mysqladmin to verify that the server is running. The following commands provide simple tests to check whether the server is up and responding to connections:

```
shell> bin/mysqladmin version
shell> bin/mysqladmin variables
```

If you cannot connect to the server, specify a -u root option to connect as root. If you have assigned a password for the root account already, you'll also need to specify -p on the command line and enter the password when prompted. For example:

```
shell> bin/mysqladmin -u root -p version
Enter password: (enter root password here)
```

The output from mysqladmin version varies slightly depending on your platform and version of MySQL, but should be similar to that shown here:

```
shell> bin/mysqladmin version
mysqladmin Ver 14.12 Distrib 5.6.32, for pc-linux-gnu on i686
...
Server version 5.6.32
Protocol version 10
Connection Localhost via UNIX socket
UNIX socket /var/lib/mysql/mysql.sock
Uptime: 14 days 5 hours 5 min 21 sec
```

```
Threads: 1 Questions: 366 Slow queries: 0
Opens: 0 Flush tables: 1 Open tables: 19
Queries per second avg: 0.000
```

To see what else you can do with mysqladmin, invoke it with the --help option.

Verify that you can shut down the server (include a -p option if the root account has a password already):

```
shell> bin/mysqladmin -u root shutdown
```

Verify that you can start the server again. Do this by using mysqld_safe or by invoking mysqld directly. For example:

```
shell> bin/mysqld_safe --user=mysql &
```

If mysqld_safe fails, see Section 3.2.1, "Troubleshooting Problems Starting the MySQL Server".

Run some simple tests to verify that you can retrieve information from the server. The output should be similar to that shown here.

Use mysqlshow to see what databases exist:

The list of installed databases may vary, but will always include the minimum of mysql and information schema.

If you specify a database name, mysqlshow displays a list of the tables within the database:

```
shell> bin/mysqlshow mysql
Database: mysql
         Tables
 columns_priv
 db
 event
 func
 general_log
 help_category
 help_keyword
 help_relation
 help_topic
 innodb_index_stats
 innodb_table_stats
 ndb_binlog_index
 plugin
 proc
 procs_priv
 proxies_priv
 servers
```

Use the <code>mysql</code> program to select information from a table in the <code>mysql</code> database:

At this point, your server is running and you can access it. To tighten security if you have not yet assigned passwords to the initial account or accounts, follow the instructions in Section 3.4, "Securing the Initial MySQL Accounts".

For more information about <code>mysql</code>, <code>mysqladmin</code>, and <code>mysqlshow</code>, see <code>mysql</code> — The MySQL Command-Line Tool, <code>mysqladmin</code> — Client for Administering a MySQL Server, and <code>mysqlshow</code> — Display Database, Table, and Column Information.

3.4 Securing the Initial MySQL Accounts

The MySQL installation process involves initializing the data directory, including the mysql database containing the grant tables that define MySQL accounts. For details, see Chapter 3, Postinstallation Setup and Testing.

This section describes how to assign passwords to the initial accounts created during the MySQL installation procedure, if you have not already done so.

The mysql.user grant table defines the initial MySQL user accounts and their access privileges:

- Some accounts have the user name root. These are superuser accounts that have all privileges and
 can do anything. If these root accounts have empty passwords, anyone can connect to the MySQL
 server as root without a password and be granted all privileges.
 - On Windows, root accounts are created that permit connections from the local host only. Connections can be made by specifying the host name localhost, the IP address 127.0.0.1, or the IPv6 address ::1. If the user selects the **Enable root access from remote machines** option during installation, the Windows installer creates another root account that permits connections from any host.
 - On Unix, each root account permits connections from the local host. Connections can be made by specifying the host name localhost, the IP address 127.0.0.1, the IPv6 address ::1, or the actual host name or IP address.

An attempt to connect to the host 127.0.0.1 normally resolves to the localhost account. However, this fails if the server is run with the --skip-name-resolve option, so the 127.0.0.1 account is useful in that case. The ::1 account is used for IPv6 connections.

- If accounts for anonymous users were created, these have an empty user name. The anonymous accounts have no password, so anyone can use them to connect to the MySQL server.
 - On Windows, there is one anonymous account that permits connections from the local host. Connections can be made by specifying a host name of localhost.
 - On Unix, each anonymous account permits connections from the local host. Connections can be
 made by specifying a host name of localhost for one of the accounts, or the actual host name or IP
 address for the other.
 - The 'root'@'localhost' account also has a row in the mysql.proxies_priv table that enables granting the PROXY privilege for ''@'', that is, for all users and all hosts. This enables root to set up proxy users, as well as to delegate to other accounts the authority to set up proxy users. See Section 5.8, "Proxy Users".

To display which accounts exist in the <code>mysql.user</code> table and check whether their passwords are empty, use the following statement:

+
User Host Passwo
root localhost root myhost.example.com root 127.0.0.1 root ::1 localhost myhost.example.com

This output indicates that there are several root and anonymous-user accounts, none of which have passwords. The output might differ on your system, but the presence of accounts with empty passwords means that your MySQL installation is unprotected until you do something about it:

- Assign a password to each MySQL root account that does not have one.
- To prevent clients from connecting as anonymous users without a password, either assign a password to each anonymous account or remove the accounts.

In addition, the <code>mysql.db</code> table contains rows that permit all accounts to access the <code>test</code> database and other databases with names that start with <code>test_</code>. This is true even for accounts that otherwise have no special privileges such as the default anonymous accounts. This is convenient for testing but inadvisable on production servers. Administrators who want database access restricted only to accounts that have permissions granted explicitly for that purpose should remove these <code>mysql.db</code> table rows.

The following instructions describe how to set up passwords for the initial MySQL accounts, first for the root accounts, then for the anonymous accounts. The instructions also cover how to remove anonymous accounts, should you prefer not to permit anonymous access at all, and describe how to remove permissive access to test databases. Replace $new_password$ in the examples with the password that you want to use. Replace $nost_name$ with the name of the server host. You can determine this name from the output of the preceding SELECT statement. For the output shown, $nost_name$ is myhost.example.com.

Note

For additional information about setting passwords, see Section 5.5, "Assigning Account Passwords". If you forget your root password after setting it, see How to Reset the Root Password.

To set up additional accounts, see Section 5.2, "Adding User Accounts".

You might want to defer setting the passwords until later, to avoid the need to specify them while you perform additional setup or testing. However, be sure to set them before using your installation for production purposes.

Note

On Windows, you can also perform the process described in this section during installation with MySQL Installer (see Installing MySQL on Microsoft Windows Using MySQL Installer). On all platforms, the MySQL distribution includes mysql_secure_installation, a command-line utility that automates much of the process of securing a MySQL installation. MySQL Workbench is available on all platforms, and also offers the ability to manage user accounts (see MySQL Workbench).

Assigning root Account Passwords

A root account password can be set several ways. The following discussion demonstrates three methods:

- Use the SET PASSWORD statement
- Use the UPDATE statement
- Use the mysqladmin command-line client program

To assign passwords using SET PASSWORD, connect to the server as root and issue a SET PASSWORD statement for each root account listed in the mysql.user table.

For Windows, do this:

```
shell> mysql -u root
mysql> SET PASSWORD FOR 'root'@'localhost' = PASSWORD('new_password');
mysql> SET PASSWORD FOR 'root'@'l27.0.0.1' = PASSWORD('new_password');
mysql> SET PASSWORD FOR 'root'@'::1' = PASSWORD('new_password');
mysql> SET PASSWORD FOR 'root'@'%' = PASSWORD('new_password');
```

The last statement is unnecessary if the mysql.user table has no root account with a host value of %.

For Unix, do this:

```
shell> mysql -u root
mysql> SET PASSWORD FOR 'root'@'localhost' = PASSWORD('new_password');
mysql> SET PASSWORD FOR 'root'@'l27.0.0.1' = PASSWORD('new_password');
mysql> SET PASSWORD FOR 'root'@'::1' = PASSWORD('new_password');
mysql> SET PASSWORD FOR 'root'@'host_name' = PASSWORD('new_password');
```

You can also use a single statement that assigns a password to all root accounts by using UPDATE to modify the mysql.user table directly. This method works on any platform:

The FLUSH statement causes the server to reread the grant tables. Without it, the password change remains unnoticed by the server until you restart it.

To assign passwords to the root accounts using mysqladmin, execute the following commands:

```
shell> mysqladmin -u root password "new_password"
shell> mysqladmin -u root -h host_name password "new_password"
```

Those commands apply both to Windows and to Unix. The double quotation marks around the password are not always necessary, but you should use them if the password contains spaces or other characters that are special to your command interpreter.

The mysqladmin method of setting the root account passwords does not work for the 'root'@'127.0.0.1' or 'root'@'::1' account. Use the SET PASSWORD method shown earlier.

After the root passwords have been set, you must supply the appropriate password whenever you connect as root to the server. For example, to shut down the server with mysqladmin, use this command:

```
shell> mysqladmin -u root -p shutdown
Enter password: (enter root password here)
```

The mysql commands in the following instructions include a -p option based on the assumption that you have assigned the root account passwords using the preceding instructions and must specify that password when connecting to the server.

Assigning Anonymous Account Passwords

To assign passwords to the anonymous accounts, connect to the server as root, then use either SET PASSWORD or UPDATE.

To use SET PASSWORD on Windows, do this:

```
shell> mysql -u root -p
Enter password: (enter root password here)
mysql> SET PASSWORD FOR ''@'localhost' = PASSWORD('new_password');
```

To use SET PASSWORD on Unix, do this:

```
shell> mysql -u root -p
Enter password: (enter root password here)
mysql> SET PASSWORD FOR ''@'localhost' = PASSWORD('new_password');
mysql> SET PASSWORD FOR ''@'host_name' = PASSWORD('new_password');
```

To set the anonymous-user account passwords with a single UPDATE statement, do this (on any platform):

The FLUSH statement causes the server to reread the grant tables. Without it, the password change remains unnoticed by the server until you restart it.

Removing Anonymous Accounts

If you prefer to remove any anonymous accounts rather than assigning them passwords, do so as follows on Windows:

```
shell> mysql -u root -p
Enter password: (enter root password here)
mysql> DROP USER ''@'localhost';
```

On Unix, remove the anonymous accounts like this:

```
shell> mysql -u root -p
Enter password: (enter root password here)
mysql> DROP USER ''@'localhost';
mysql> DROP USER ''@'host_name';
```

Securing Test Databases

By default, the <code>mysql</code>. db table contains rows that permit access by any user to the <code>test</code> database and other databases with names that start with <code>test_</code>. (These rows have an empty <code>User</code> column value, which for access-checking purposes matches any user name.) This means that such databases can be used even by accounts that otherwise possess no privileges. If you want to remove any-user access to test databases, do so as follows:

```
shell> mysql -u root -p
Enter password: (enter root password here)
mysql> DELETE FROM mysql.db WHERE Db LIKE 'test%';
mysql> FLUSH PRIVILEGES;
```

The FLUSH statement causes the server to reread the grant tables. Without it, the privilege change remains unnoticed by the server until you restart it.

With the preceding change, only users who have global database privileges or privileges granted explicitly for the test database can use it. However, if you prefer that the database not exist at all, drop it:

```
mysql> DROP DATABASE test;
```

3.5 Starting and Stopping MySQL Automatically

This section discusses methods for starting and stopping the MySQL server.

Generally, you start the mysqld server in one of these ways:

- Invoke mysqld directly. This works on any platform.
- On Windows, you can set up a MySQL service that runs automatically when Windows starts. See Starting MySQL as a Windows Service.
- On Unix and Unix-like systems, you can invoke mysqld_safe, which tries to determine the proper
 options for mysqld and then runs it with those options. See mysqld_safe MySQL Server Startup
 Script.
- On systems that use System V-style run directories (that is, /etc/init.d and run-level specific directories), invoke mysql.server. This script is used primarily at system startup and shutdown. It usually is installed under the name mysql. The mysql.server script starts the server by invoking mysqld_safe. See mysql.server MySQL Server Startup Script.
- On OS X, install a launchd daemon to enable automatic MySQL startup at system startup. The daemon starts the server by invoking mysqld_safe. For details, see Installing a MySQL Launch Daemon. A

MySQL Preference Pane also provides control for starting and stopping MySQL through the System Preferences. See Installing and Using the MySQL Preference Pane.

 On Solaris/OpenSolaris, use the service management framework (SMF) system to initiate and control MySQL startup. For more information, see Installing MySQL on OpenSolaris Using IPS.

The mysqld_safe and mysql.server scripts, Solaris/OpenSolaris SMF, and the OS X Startup Item (or MySQL Preference Pane) can be used to start the server manually, or automatically at system startup time. mysql.server and the Startup Item also can be used to stop the server.

The following table shows which option groups the server and startup scripts read from option files.

Table 3.1 MySQL Startup Scripts and Supported Server Option Groups

Script	Option Groups	
mysqld	[mysqld], [server], [mysqld-major_version]	
mysqld_safe	[mysqld],[server],[mysqld_safe]	
mysql.server	[mysqld], [mysql.server], [server]	

[mysqld-major_version] means that groups with names like [mysqld-5.5] and [mysqld-5.6] are read by servers having versions 5.5.x, 5.6.x, and so forth. This feature can be used to specify options that can be read only by servers within a given release series.

For backward compatibility, mysql.server also reads the [mysql_server] group and mysqld_safe also reads the [safe_mysqld] group. However, you should update your option files to use the [mysql.server] and [mysqld_safe] groups instead.

For more information on MySQL configuration files and their structure and contents, see Using Option Files.

34

Chapter 4 The MySQL Access Privilege System

Table of Contents

36
40
46
48
51
52
53

The primary function of the MySQL privilege system is to authenticate a user who connects from a given host and to associate that user with privileges on a database such as SELECT, INSERT, UPDATE, and DELETE. Additional functionality includes the ability to have anonymous users and to grant privileges for MySQL-specific functions such as LOAD DATA INFILE and administrative operations.

There are some things that you cannot do with the MySQL privilege system:

- You cannot explicitly specify that a given user should be denied access. That is, you cannot explicitly
 match a user and then refuse the connection.
- You cannot specify that a user has privileges to create or drop tables in a database but not to create or drop the database itself.
- A password applies globally to an account. You cannot associate a password with a specific object such as a database, table, or routine.

The user interface to the MySQL privilege system consists of SQL statements such as CREATE USER, GRANT, and REVOKE. See Account Management Statements.

Internally, the server stores privilege information in the grant tables of the mysql database (that is, in the database named mysql). The MySQL server reads the contents of these tables into memory when it starts and bases access-control decisions on the in-memory copies of the grant tables.

The MySQL privilege system ensures that all users may perform only the operations permitted to them. As a user, when you connect to a MySQL server, your identity is determined by *the host from which you connect* and *the user name you specify*. When you issue requests after connecting, the system grants privileges according to your identity and *what you want to do*.

MySQL considers both your host name and user name in identifying you because there is no reason to assume that a given user name belongs to the same person on all hosts. For example, the user joe who connects from office.example.com need not be the same person as the user joe who connects from home.example.com. MySQL handles this by enabling you to distinguish users on different hosts that happen to have the same name: You can grant one set of privileges for connections by joe from office.example.com, and a different set of privileges for connections by joe from home.example.com. To see what privileges a given account has, use the SHOW GRANTS statement. For example:

```
SHOW GRANTS FOR 'joe'@'office.example.com';
SHOW GRANTS FOR 'joe'@'home.example.com';
```

MySQL access control involves two stages when you run a client program that connects to the server:

Stage 1: The server accepts or rejects the connection based on your identity and whether you can verify your identity by supplying the correct password.

Stage 2: Assuming that you can connect, the server checks each statement you issue to determine whether you have sufficient privileges to perform it. For example, if you try to select rows from a table in a database or drop a table from the database, the server verifies that you have the SELECT privilege for the table or the DROP privilege for the database.

For a more detailed description of what happens during each stage, see Section 4.4, "Access Control, Stage 1: Connection Verification", and Section 4.5, "Access Control, Stage 2: Request Verification".

If your privileges are changed (either by yourself or someone else) while you are connected, those changes do not necessarily take effect immediately for the next statement that you issue. For details about the conditions under which the server reloads the grant tables, see Section 4.6, "When Privilege Changes Take Effect".

For general security-related advice, see Chapter 2, *General Security Issues*. For help in diagnosing privilege-related problems, see Section 4.7, "Troubleshooting Problems Connecting to MySQL".

4.1 Privileges Provided by MySQL

MySQL provides privileges that apply in different contexts and at different levels of operation:

- Administrative privileges enable users to manage operation of the MySQL server. These privileges are global because they are not specific to a particular database.
- Database privileges apply to a database and to all objects within it. These privileges can be granted for specific databases, or globally so that they apply to all databases.
- Privileges for database objects such as tables, indexes, views, and stored routines can be granted for specific objects within a database, for all objects of a given type within a database (for example, all tables in a database), or globally for all objects of a given type in all databases).

Information about account privileges is stored in the user, db, tables_priv, columns_priv, and procs_priv tables in the mysql database (see Section 4.2, "Grant Tables"). The MySQL server reads the contents of these tables into memory when it starts and reloads them under the circumstances indicated in Section 4.6, "When Privilege Changes Take Effect". Access-control decisions are based on the in-memory copies of the grant tables.

Some releases of MySQL introduce changes to the structure of the grant tables to add new privileges or features. To make sure that you can take advantage of any new capabilities, update your grant tables to have the current structure whenever you update to a new version of MySQL. See mysql_upgrade — Check and Upgrade MySQL Tables.

The following table shows the privilege names used at the SQL level in the GRANT and REVOKE statements, along with the column name associated with each privilege in the grant tables and the context in which the privilege applies.

Table 4.1 Permissible Privileges for GRANT and REVOKE

Privilege	Column	Context
CREATE	Create_priv	databases, tables, or indexes
DROP	Drop_priv	databases, tables, or views
GRANT OPTION	Grant_priv	databases, tables, or stored routines
LOCK TABLES	Lock_tables_priv	databases

Privilege	Column	Context
REFERENCES	References_priv	databases or tables
EVENT	Event_priv	databases
ALTER	Alter_priv	tables
DELETE	Delete_priv	tables
INDEX	Index_priv	tables
INSERT	Insert_priv	tables or columns
SELECT	Select_priv	tables or columns
UPDATE	Update_priv	tables or columns
CREATE TEMPORARY TABLES	Create_tmp_table_priv	tables
TRIGGER	Trigger_priv	tables
CREATE VIEW	Create_view_priv	views
SHOW VIEW	Show_view_priv	views
ALTER ROUTINE	Alter_routine_priv	stored routines
CREATE ROUTINE	Create_routine_priv	stored routines
EXECUTE	Execute_priv	stored routines
FILE	File_priv	file access on server host
CREATE TABLESPACE	Create_tablespace_priv	server administration
CREATE USER	Create_user_priv	server administration
PROCESS	Process_priv	server administration
PROXY	see proxies_priv table	server administration
RELOAD	Reload_priv	server administration
REPLICATION CLIENT	Repl_client_priv	server administration
REPLICATION SLAVE	Repl_slave_priv	server administration
SHOW DATABASES	Show_db_priv	server administration
SHUTDOWN	Shutdown_priv	server administration
SUPER	Super_priv	server administration
ALL [PRIVILEGES]		server administration
USAGE		server administration

The following list provides a general description of each privilege available in MySQL. Particular SQL statements might have more specific privilege requirements than indicated here. If so, the description for the statement in question provides the details.

- The ALL or ALL PRIVILEGES privilege specifier is shorthand. It stands for "all privileges available at a given privilege level" (except GRANT OPTION). For example, granting ALL at the global or table level grants all global privileges or all table-level privileges.
- The ALTER privilege enables use of ALTER TABLE to change the structure of tables. ALTER TABLE also requires the CREATE and INSERT privileges. Renaming a table requires ALTER and DROP on the old table, CREATE, and INSERT on the new table.
- The ALTER ROUTINE privilege is needed to alter or drop stored routines (procedures and functions).

- The CREATE privilege enables creation of new databases and tables.
- The CREATE ROUTINE privilege is needed to create stored routines (procedures and functions).
- The CREATE TABLESPACE privilege is needed to create, alter, or drop tablespaces and log file groups.
- The CREATE TEMPORARY TABLES privilege enables the creation of temporary tables using the CREATE TEMPORARY TABLE statement.

As of MySQL 5.6.3, after a session has created a temporary table, the server performs no further privilege checks on the table. The creating session can perform any operation on the table, such as DROP TABLE, INSERT, UPDATE, or SELECT.

One implication of this behavior is that a session can manipulate its temporary tables even if the current user has no privilege to create them. Suppose that the current user does not have the CREATE TEMPORARY TABLES privilege but is able to execute a DEFINER-context stored procedure that executes with the privileges of a user who does have CREATE TEMPORARY TABLES and that creates a temporary table. While the procedure executes, the session uses the privileges of the defining user. After the procedure returns, the effective privileges revert to those of the current user, which can still see the temporary table and perform any operation on it.

Before MySQL 5.6.3, other operations on a temporary table, such as INSERT, UPDATE, or SELECT, require additional privileges for those operations for the database containing the temporary table, or for the nontemporary table of the same name.

To keep privileges for temporary and nontemporary tables separate, a common workaround for this situation is to create a database dedicated to the use of temporary tables. Then for that database, a user can be granted the CREATE TEMPORARY TABLES privilege, along with any other privileges required for temporary table operations done by that user.

- The CREATE USER privilege enables use of ALTER USER, CREATE USER, DROP USER, RENAME USER, and REVOKE ALL PRIVILEGES.
- The CREATE VIEW privilege enables use of CREATE VIEW.
- The DELETE privilege enables rows to be deleted from tables in a database.
- The DROP privilege enables you to drop (remove) existing databases, tables, and views. The DROP privilege is required in order to use the statement ALTER TABLE ... DROP PARTITION on a partitioned table. The DROP privilege is also required for TRUNCATE TABLE. If you grant the DROP privilege for the mysql database to a user, that user can drop the database in which the MySQL access privileges are stored.
- The EVENT privilege is required to create, alter, drop, or see events for the Event Scheduler.
- The EXECUTE privilege is required to execute stored routines (procedures and functions).
- The FILE privilege gives you permission to read and write files on the server host using the LOAD DATA INFILE and SELECT ... INTO OUTFILE statements and the LOAD_FILE() function. A user who has the FILE privilege can read any file on the server host that is either world-readable or readable by the MySQL server. (This implies the user can read any file in any database directory, because the server can access any of those files.) The FILE privilege also enables the user to create new files in any directory where the MySQL server has write access. This includes the server's data directory containing the files that implement the privilege tables. As a security measure, the server will not overwrite existing files.

To limit the location in which files can be read and written, set the secure_file_priv system to a specific directory. See Server System Variables.

- The GRANT OPTION privilege enables you to give to other users or remove from other users those privileges that you yourself possess.
- The INDEX privilege enables you to create or drop (remove) indexes. INDEX applies to existing tables. If you have the CREATE privilege for a table, you can include index definitions in the CREATE TABLE statement.
- The INSERT privilege enables rows to be inserted into tables in a database. INSERT is also required for the ANALYZE TABLE, OPTIMIZE TABLE, and REPAIR TABLE table-maintenance statements.
- The LOCK TABLES privilege enables the use of explicit LOCK TABLES statements to lock tables for which you have the SELECT privilege. This includes the use of write locks, which prevents other sessions from reading the locked table.
- The PROCESS privilege pertains to display of information about the threads executing within the server (that is, information about the statements being executed by sessions). The privilege enables use of SHOW PROCESSLIST or mysqladmin processlist to see threads belonging to other accounts; you can always see your own threads. The PROCESS privilege also enables use of SHOW ENGINE.
- The PROXY privilege enables a user to impersonate or become known as another user. See Section 5.8, "Proxy Users".
- The REFERENCES privilege is unused before MySQL 5.6.22. As of 5.6.22, creation of a foreign key constraint requires at least one of the SELECT, INSERT, UPDATE, DELETE, or REFERENCES privileges for the parent table.
- The RELOAD privilege enables use of the FLUSH statement. It also enables mysqladmin commands that are equivalent to FLUSH operations: flush-hosts, flush-logs, flush-privileges, flush-status, flush-tables, flush-threads, refresh, and reload.

The reload command tells the server to reload the grant tables into memory. flush-privileges is a synonym for reload. The refresh command closes and reopens the log files and flushes all tables. The other flush-xxx commands perform functions similar to refresh, but are more specific and may be preferable in some instances. For example, if you want to flush just the log files, flush-logs is a better choice than refresh.

- The REPLICATION CLIENT privilege enables the use of SHOW MASTER STATUS and SHOW SLAVE STATUS. In MySQL 5.6.6 and later, it also enables the use of the SHOW BINARY LOGS statement.
- The REPLICATION SLAVE privilege should be granted to accounts that are used by slave servers to connect to the current server as their master. Without this privilege, the slave cannot request updates that have been made to databases on the master server.
- The SELECT privilege enables you to select rows from tables in a database. SELECT statements require the SELECT privilege only if they actually retrieve rows from a table. Some SELECT statements do not access tables and can be executed without permission for any database. For example, you can use SELECT as a simple calculator to evaluate expressions that make no reference to tables:

```
SELECT 1+1;
SELECT PI()*2;
```

The SELECT privilege is also needed for other statements that read column values. For example, SELECT is needed for columns referenced on the right hand side of col_name=expr assignment in UPDATE statements or for columns named in the WHERE clause of DELETE or UPDATE statements.

• The SHOW DATABASES privilege enables the account to see database names by issuing the SHOW DATABASE statement. Accounts that do not have this privilege see only databases for which they have

some privileges, and cannot use the statement at all if the server was started with the --skip-show-database option. Note that *any* global privilege is a privilege for the database.

- The SHOW VIEW privilege enables use of SHOW CREATE VIEW.
- The SHUTDOWN privilege enables use of the mysqladmin shutdown command and the mysql_shutdown() C API function. There is no corresponding SQL statement.
- The SUPER privilege enables an account to use CHANGE MASTER TO, KILL or mysqladmin kill to kill threads belonging to other accounts (you can always kill your own threads), PURGE BINARY LOGS, configuration changes using SET GLOBAL to modify global system variables, the mysqladmin debug command, enabling or disabling logging, performing updates even if the read_only system variable is enabled, starting and stopping replication on slave servers, specification of any account in the DEFINER attribute of stored programs and views, and enables you to connect (once) even if the connection limit controlled by the max_connections system variable is reached.

To create or alter stored functions if binary logging is enabled, you may also need the SUPER privilege, as described in Binary Logging of Stored Programs.

• The TRIGGER privilege enables trigger operations. You must have this privilege for a table to create, drop, execute, or display triggers for that table.

When a trigger is activated (by a user who has privileges to execute INSERT, UPDATE, or DELETE statements for the table associated with the trigger), trigger execution requires that the user who defined the trigger still have the TRIGGER privilege.

- The UPDATE privilege enables rows to be updated in tables in a database.
- The USAGE privilege specifier stands for "no privileges." It is used at the global level with GRANT to
 modify account attributes such as resource limits or SSL characteristics without affecting existing
 account privileges.

It is a good idea to grant to an account only those privileges that it needs. You should exercise particular caution in granting the FILE and administrative privileges:

- The FILE privilege can be abused to read into a database table any files that the MySQL server can read on the server host. This includes all world-readable files and files in the server's data directory. The table can then be accessed using SELECT to transfer its contents to the client host.
- The GRANT OPTION privilege enables users to give their privileges to other users. Two users that have different privileges and with the GRANT OPTION privilege are able to combine privileges.
- The ALTER privilege may be used to subvert the privilege system by renaming tables.
- The SHUTDOWN privilege can be abused to deny service to other users entirely by terminating the server.
- The PROCESS privilege can be used to view the plain text of currently executing statements, including statements that set or change passwords.
- The SUPER privilege can be used to terminate other sessions or change how the server operates.
- Privileges granted for the mysql database itself can be used to change passwords and other access
 privilege information. Passwords are stored encrypted, so a malicious user cannot simply read them to
 know the plain text password. However, a user with write access to the user table Password column
 can change an account's password, and then connect to the MySQL server using that account.

4.2 Grant Tables

The mysql system database includes several grant tables that contain information about user accounts and the privileges held by them. This section describes those tables. For information about other tables in the system database, see The mysql System Database.

Normally, to manipulate the contents of grant tables, you modify them indirectly by using account-management statements such as CREATE USER, GRANT, and REVOKE to set up accounts and control the privileges available to each one. See Account Management Statements. The discussion here describes the underlying structure of the grant tables and how the server uses their contents when interacting with clients.

Note

Direct modification of grant tables using statements such as INSERT, UPDATE, or DELETE is discouraged and done at your own risk. The server is free to ignore rows that become malformed as a result of such modifications.

These mysql database tables contain grant information:

- user: User accounts, global privileges, and other non-privilege columns.
- db: Database-level privileges.
- host: Obsolete. MySQL install operations do not create this table as of MySQL 5.6.7.
- tables priv: Table-level privileges.
- columns priv: Column-level privileges.
- procs_priv: Stored procedure and function privileges.
- proxies_priv: Proxy-user privileges.

Each grant table contains scope columns and privilege columns:

- Scope columns determine the scope of each row in the tables; that is, the context in which the row applies. For example, a user table row with Host and User values of 'thomas.loc.gov' and 'bob' applies to authenticating connections made to the server from the host thomas.loc.gov by a client that specifies a user name of bob. Similarly, a db table row with Host, User, and Db column values of 'thomas.loc.gov', 'bob' and 'reports' applies when bob connects from the host thomas.loc.gov to access the reports database. The tables_priv and columns_priv tables contain scope columns indicating tables or table/column combinations to which each row applies. The procs priv scope columns indicate the stored routine to which each row applies.
- Privilege columns indicate which privileges a table row grants; that is, which operations it permits to
 be performed. The server combines the information in the various grant tables to form a complete
 description of a user's privileges. Section 4.5, "Access Control, Stage 2: Request Verification", describes
 the rules for this.

The server uses the grant tables in the following manner:

• The user table scope columns determine whether to reject or permit incoming connections. For permitted connections, any privileges granted in the user table indicate the user's global privileges. Any privileges granted in this table apply to *all* databases on the server.

Caution

Because any global privilege is considered a privilege for all databases, any global privilege enables a user to see all database names with SHOW DATABASES or by examining the SCHEMATA table of INFORMATION_SCHEMA.

- The db table scope columns determine which users can access which databases from which hosts. The privilege columns determine the permitted operations. A privilege granted at the database level applies to the database and to all objects in the database, such as tables and stored programs.
- The tables_priv and columns_priv tables are similar to the db table, but are more fine-grained: They apply at the table and column levels rather than at the database level. A privilege granted at the table level applies to the table and to all its columns. A privilege granted at the column level applies only to a specific column.
- The procs_priv table applies to stored routines (procedures and functions). A privilege granted at the routine level applies only to a single procedure or function.
- The proxies_priv table indicates which users can act as proxies for other users and whether a user can grant the PROXY privilege to other users.

The server uses the user and db tables in the mysql database at both the first and second stages of access control (see Chapter 4, *The MySQL Access Privilege System*). The columns in the user and db tables are shown here.

Table 4.2 user and db Table Columns

Table Name	user	db
Scope columns	Host	Host
	User	Db
	Password	User
Privilege columns	Select_priv	Select_priv
	Insert_priv	Insert_priv
	Update_priv	Update_priv
	Delete_priv	Delete_priv
	Index_priv	Index_priv
	Alter_priv	Alter_priv
	Create_priv	Create_priv
	Drop_priv	Drop_priv
	Grant_priv	Grant_priv
	Create_view_priv	Create_view_priv
	Show_view_priv	Show_view_priv
	Create_routine_priv	Create_routine_priv
	Alter_routine_priv	Alter_routine_priv
	Execute_priv	Execute_priv
	Trigger_priv	Trigger_priv
	Event_priv	Event_priv
	Create_tmp_table_priv	Create_tmp_table_priv
	Lock_tables_priv	Lock_tables_priv
	References_priv	References_priv
	Reload_priv	
	Shutdown_priv	

Table Name	user	db
	Process_priv	
	File_priv	
	Show_db_priv	
	Super_priv	
	Repl_slave_priv	
	Repl_client_priv	
	Create_user_priv	
	Create_tablespace_priv	
Security columns	ssl_type	
	ssl_cipher	
	x509_issuer	
	x509_subject	
	plugin	
	authentication_string	
	password_expired	
Resource control columns	max_questions	
	max_updates	
	max_connections	
	max_user_connections	

The user table plugin, Password, and authentication_string columns store authentication plugin and credential information.

If an account row names a plugin in the plugin column, the server uses it to authenticate connection attempts for the account. It is up to the plugin whether it uses the Password and authentication_string column values.

If the plugin column for an account row is empty, the server authenticates the account using the mysql_native_password or mysql_old_password plugin implicitly, depending on the format of the password hash in the Password column. If the Password value is empty or a 4.1 password hash (41 characters), the server uses mysql_native_password. If the password value is a pre-4.1 password hash (16 characters), the server uses mysql_old_password. (For additional information about these hash formats, see Section 2.2.4, "Password Hashing in MySQL".) Clients must match the password in the Password column of the account row.

The password_expired column was added in MySQL 5.6.6 to permit DBAs to expire account passwords and require users to reset their password. The default password_expired value is 'N', but can be set to 'Y' with the ALTER USER statement. After an account's password has been expired, all operations performed by the account in subsequent connections to the server result in an error until the user issues a SET PASSWORD statement to establish a new account password.

It is possible after password expiration to "reset" a password by setting it to its current value. As a matter of good policy, it is preferable to choose a different password.

Caution

In MySQL 5.6.6, ALTER USER also sets the Password column to the empty string, so do not use this statement until 5.6.7.

During the second stage of access control, the server performs request verification to ensure that each client has sufficient privileges for each request that it issues. In addition to the user and db grant tables, the server may also consult the tables_priv and columns_priv tables for requests that involve tables. The latter tables provide finer privilege control at the table and column levels. They have the columns shown in the following table.

Table 4.3 tables_priv and columns_priv Table Columns

Table Name	tables_priv	columns_priv
Scope columns	Host	Host
	Db	Db
	User	User
	Table_name	Table_name
		Column_name
Privilege columns	Table_priv	Column_priv
	Column_priv	
Other columns	Timestamp	Timestamp
	Grantor	

The Timestamp and Grantor columns are set to the current timestamp and the CURRENT_USER value, respectively, but are otherwise unused.

For verification of requests that involve stored routines, the server may consult the procs_priv table, which has the columns shown in the following table.

Table 4.4 procs_priv Table Columns

Table Name	procs_priv
Scope columns	Host
	Db
	User
	Routine_name
	Routine_type
Privilege columns	Proc_priv
Other columns	Timestamp
	Grantor

The Routine_type column is an ENUM column with values of 'FUNCTION' or 'PROCEDURE' to indicate the type of routine the row refers to. This column enables privileges to be granted separately for a function and a procedure with the same name.

The Timestamp and Grantor columns are unused.

The proxies_priv table records information about proxy accounts. It has these columns:

- Host, User: The proxy account; that is, the account that has the PROXY privilege for the proxied account.
- Proxied_host, Proxied_user: The proxied account.
- Grantor, Timestamp: Unused.
- With grant: Whether the proxy account can grant the PROXY privilege to other accounts.

For an account to be able to grant the PROXY privilege to other accounts, it must have a row in the proxies_priv table with With_grant set to 1 and Proxied_host and Proxied_user set to indicate the account or accounts for which the privilege can be granted. For example, the 'root'@'localhost' account created during MySQL installation has a row in the proxies_priv table that enables granting the PROXY privilege for ''@'', that is, for all users and all hosts. This enables root to set up proxy users, as well as to delegate to other accounts the authority to set up proxy users. See Section 5.8, "Proxy Users".

Scope columns in the grant tables contain strings. The default value for each is the empty string. The following table shows the number of characters permitted in each column.

Table 4.5 Grant Table Scope Column Lengths

Column Name	Maximum Permitted Characters
Host, Proxied_host	60
User, Proxied_user	16
Password	41
Db	64
Table_name	64
Column_name	64
Routine_name	64

For access-checking purposes, comparisons of User, Proxied_user, Password, Db, and Table_name values are case sensitive. Comparisons of Host, Proxied_host, Column_name, and Routine_name values are not case sensitive.

The user and db tables list each privilege in a separate column that is declared as ENUM('N', 'Y')

DEFAULT 'N'. In other words, each privilege can be disabled or enabled, with the default being disabled.

The tables_priv, columns_priv, and procs_priv tables declare the privilege columns as SET columns. Values in these columns can contain any combination of the privileges controlled by the table. Only those privileges listed in the column value are enabled.

Table 4.6 Set-Type Privilege Column Values

Table Name	Column Name	Possible Set Elements
tables_priv	Table_priv	'Select', 'Insert', 'Update', 'Delete', 'Create', 'Drop', 'Grant', 'References', 'Index', 'Alter', 'Create View', 'Show view', 'Trigger'
tables_priv	Column_priv	'Select', 'Insert', 'Update', 'References'
columns_priv	Column_priv	'Select', 'Insert', 'Update', 'References'
procs_priv	Proc_priv	'Execute', 'Alter Routine', 'Grant'

Only the user table specifies administrative privileges, such as RELOAD and SHUTDOWN. Administrative operations are operations on the server itself and are not database-specific, so there is no reason to list these privileges in the other grant tables. Consequently, the server need consult only the user table to determine whether a user can perform an administrative operation.

The FILE privilege also is specified only in the user table. It is not an administrative privilege as such, but a user's ability to read or write files on the server host is independent of the database being accessed.

The server reads the contents of the grant tables into memory when it starts. You can tell it to reload the tables by issuing a FLUSH PRIVILEGES statement or executing a mysqladmin flush-privileges or mysqladmin reload command. Changes to the grant tables take effect as indicated in Section 4.6, "When Privilege Changes Take Effect".

When you modify an account, it is a good idea to verify that your changes have the intended effect. To check the privileges for a given account, use the SHOW GRANTS statement. For example, to determine the privileges that are granted to an account with user name and host name values of bob and pc84.example.com, use this statement:

```
SHOW GRANTS FOR 'bob'@'pc84.example.com';
```

4.3 Specifying Account Names

MySQL account names consist of a user name and a host name. This enables creation of accounts for users with the same name who can connect from different hosts. This section describes how to write account names, including special values and wildcard rules.

In SQL statements such as CREATE USER, GRANT, and SET PASSWORD, write account names using the following rules:

- Syntax for account names is 'user name'@'host name'.
- An account name consisting only of a user name is equivalent to 'user_name'@'%'. For example, 'me' is equivalent to 'me'@'%'.
- The user name and host name need not be quoted if they are legal as unquoted identifiers. Quotes are necessary to specify a user_name string containing special characters or wildcard characters (such as "\"); for example, 'test-user'@'\", com'.
- Quote user names and host names as identifiers or as strings, using either backticks ("`"), single quotation marks ("""), or double quotation marks (""").
- The user name and host name parts, if quoted, must be quoted separately. That is, write 'me'@'localhost', not 'me@localhost'; the latter is interpreted as 'me@localhost'@'%'.
- A reference to the CURRENT_USER or CURRENT_USER() function is equivalent to specifying the current client's user name and host name literally.

MySQL stores account names in grant tables in the mysql database using separate columns for the user name and host name parts:

- The user table contains one row for each account. The User and Host columns store the user name and host name. This table also indicates which global privileges the account has.
- Other grant tables indicate privileges an account has for databases and objects within databases. These tables have User and Host columns to store the account name. Each row in these tables associates with the account in the user table that has the same User and Host values.

For additional detail about grant table structure, see Section 4.2, "Grant Tables".

User names and host names have certain special values or wildcard conventions, as described following.

A user name is either a nonblank value that literally matches the user name for incoming connection attempts, or a blank value (empty string) that matches any user name. An account with a blank user name is an anonymous user. To specify an anonymous user in SQL statements, use a quoted empty user name part, such as ''@'localhost'.

The host name part of an account name can take many forms, and wildcards are permitted:

- A host value can be a host name or an IP address (IPv4 or IPv6). The name 'localhost' indicates the local host. The IP address '127.0.0.1' indicates the IPv4 loopback interface. The IP address '::1' indicates the IPv6 loopback interface.
- You can use the wildcard characters "%" and "_" in host name or IP address values. These have the same meaning as for pattern-matching operations performed with the LIKE operator. For example, a host value of '%' matches any host name, whereas a value of '%' matches any host in the mysql.com domain. '192.168.1.%' matches any host in the 192.168.1 class C network.

Because you can use IP wildcard values in host values (for example, '192.168.1.%' to match every host on a subnet), someone could try to exploit this capability by naming a host 192.168.1.somewhere.com. To foil such attempts, MySQL disallows matching on host names that start with digits and a dot. Thus, if you have a host named something like 1.2.example.com, its name never matches the host part of account names. An IP wildcard value can match only IP addresses, not host names.

 For a host value specified as an IPv4 address, you can specify a netmask indicating how many address bits to use for the network number. Netmask notation cannot be used for IPv6 addresses.

The syntax is *host_ip/netmask*. For example:

```
CREATE USER 'david'@'192.58.197.0/255.255.0';
```

This enables david to connect from any client host having an IP address *client_ip* for which the following condition is true:

```
client_ip & netmask = host_ip
```

That is, for the CREATE USER statement just shown:

```
client_ip & 255.255.255.0 = 192.58.197.0
```

IP addresses that satisfy this condition and can connect to the MySQL server are those in the range from 192.58.197.0 to 192.58.197.255.

A netmask typically begins with bits set to 1, followed by bits set to 0. Examples:

- 192.0.0.0/255.0.0.0: Any host on the 192 class A network
- 192.168.0.0/255.255.0.0: Any host on the 192.168 class B network
- 192.168.1.0/255.255.255.0: Any host on the 192.168.1 class C network
- 192.168.1.1: Only the host with this specific IP address

The following netmask will not work because it masks 28 bits, and 28 is not a multiple of 8:

```
192.168.0.1/255.255.255.240
```

The server performs matching of host values in account names against the client host using the value returned by the system DNS resolver for the client host name or IP address. Except in the case that the account host value is specified using netmask notation, this comparison is performed as a string match, even for an account host value given as an IP address. This means that you should specify account host values in the same format used by DNS. Here are examples of problems to watch out for:

- Suppose that a host on the local network has a fully qualified name of host1.example.com. If DNS returns name lookups for this host as host1.example.com, use that name in account host values. But if DNS returns just host1, use host1 instead.
- If DNS returns the IP address for a given host as 192.168.1.2, that will match an account host value of 192.168.1.2 but not 192.168.01.2. Similarly, it will match an account host pattern like 192.168.1. % but not 192.168.01.%.

To avoid problems like this, it is advisable to check the format in which your DNS returns host names and addresses, and use values in the same format in MySQL account names.

4.4 Access Control, Stage 1: Connection Verification

When you attempt to connect to a MySQL server, the server accepts or rejects the connection based on your identity and whether you can verify your identity by supplying the correct password. If not, the server denies access to you completely. Otherwise, the server accepts the connection, and then enters Stage 2 and waits for requests.

Credential checking is performed using the three user table scope columns (Host, User, and Password). The server accepts the connection only if the Host and User columns in some user table row match the client host name and user name and the client supplies the password specified in that row. The rules for permissible Host and User values are given in Section 4.3, "Specifying Account Names".

Your identity is based on two pieces of information:

- The client host from which you connect
- Your MySQL user name

If the User column value is nonblank, the user name in an incoming connection must match exactly. If the User value is blank, it matches any user name. If the user table row that matches an incoming connection has a blank user name, the user is considered to be an anonymous user with no name, not a user with the name that the client actually specified. This means that a blank user name is used for all further access checking for the duration of the connection (that is, during Stage 2).

The Password column can be blank. This is not a wildcard and does not mean that any password matches. It means that the user must connect without specifying a password. If the server authenticates a client using a plugin, the authentication method that the plugin implements may or may not use the password in the Password column. In this case, it is possible that an external password is also used to authenticate to the MySQL server.

Nonblank Password values in the user table represent encrypted passwords. MySQL does not store passwords in cleartext form for anyone to see. Rather, the password supplied by a user who is attempting to connect is encrypted (using the PASSWORD() function). The encrypted password then is used during the

connection process when checking whether the password is correct. This is done without the encrypted password ever traveling over the connection. See Section 5.1, "User Names and Passwords".

From MySQL's point of view, the encrypted password is the *real* password, so you should never give anyone access to it. In particular, *do not give nonadministrative users read access to tables in the mysql database.*

The following table shows how various combinations of User and Host values in the user table apply to incoming connections.

User Value	Host Value	Permissible Connections
'fred'	'thomas.loc.gov'	fred, connecting from thomas.loc.gov
1-1	'thomas.loc.gov'	Any user, connecting from thomas.loc.gov
'fred'	181	fred, connecting from any host
1.1	181	Any user, connecting from any host
'fred'	'%.loc.gov'	fred, connecting from any host in the loc.gov domain
'fred'	'x.y.%'	fred, connecting from x.y.net, x.y.com, x.y.edu, and so on; this is probably not useful
'fred'	'192.168.10.177'	fred, connecting from the host with IP address 192.168.10.177
'fred'	'192.168.10.%'	fred, connecting from any host in the 192.168.10 class C subnet
'fred'	'192.168.10.0/255.255.255.0	Same as previous example

It is possible for the client host name and user name of an incoming connection to match more than one row in the user table. The preceding set of examples demonstrates this: Several of the entries shown match a connection from thomas.loc.gov by fred.

When multiple matches are possible, the server must determine which of them to use. It resolves this issue as follows:

- Whenever the server reads the user table into memory, it sorts the rows.
- When a client attempts to connect, the server looks through the rows in sorted order.
- The server uses the first row that matches the client host name and user name.

The server uses sorting rules that order rows with the most-specific Host values first. Literal host names and IP addresses are the most specific. (The specificity of a literal IP address is not affected by whether it has a netmask, so 192.168.1.13 and 192.168.1.0/255.255.255.0 are considered equally specific.) The pattern '%' means "any host" and is least specific. The empty string '' also means "any host" but sorts after '%'. Rows with the same Host value are ordered with the most-specific User values first (a blank User value means "any user" and is least specific). For rows with equally-specific Host and User values, the order is indeterminate.

To see how this works, suppose that the user table looks like this:

When the server reads the table into memory, it sorts the rows using the rules just described. The result after sorting looks like this:

When a client attempts to connect, the server looks through the sorted rows and uses the first match found. For a connection from localhost by jeffrey, two of the rows from the table match: the one with Host and User values of 'localhost' and '', and the one with values of '%' and 'jeffrey'. The 'localhost' row appears first in sorted order, so that is the one the server uses.

Here is another example. Suppose that the user table looks like this:

The sorted table looks like this:

A connection by jeffrey from thomas.loc.gov is matched by the first row, whereas a connection by jeffrey from any host is matched by the second.

Note

It is a common misconception to think that, for a given user name, all rows that explicitly name that user are used first when the server attempts to find a match for the connection. This is not true. The preceding example illustrates this, where a connection from thomas.loc.gov by jeffrey is first matched not by the row containing 'jeffrey' as the User column value, but by the row with no user name. As a result, jeffrey is authenticated as an anonymous user, even though he specified a user name when connecting.

If you are able to connect to the server, but your privileges are not what you expect, you probably are being authenticated as some other account. To find out what account the server used to authenticate you, use the <code>CURRENT_USER()</code> function. (See Information Functions.) It returns a value in <code>user_name@host_name</code> format that indicates the <code>User</code> and <code>Host</code> values from the matching <code>user</code> table row. Suppose that <code>jeffrey</code> connects and issues the following query:

The result shown here indicates that the matching user table row had a blank User column value. In other words, the server is treating jeffrey as an anonymous user.

Another way to diagnose authentication problems is to print out the user table and sort it by hand to see where the first match is being made.

4.5 Access Control, Stage 2: Request Verification

After you establish a connection, the server enters Stage 2 of access control. For each request that you issue through that connection, the server determines what operation you want to perform, then checks whether you have sufficient privileges to do so. This is where the privilege columns in the grant tables come into play. These privileges can come from any of the user, db, tables_priv, columns_priv, or procs_priv tables. (You may find it helpful to refer to Section 4.2, "Grant Tables", which lists the columns present in each of the grant tables.)

The user table grants privileges that are assigned to you on a global basis and that apply no matter what the default database is. For example, if the user table grants you the DELETE privilege, you can delete rows from any table in any database on the server host! It is wise to grant privileges in the user table only to people who need them, such as database administrators. For other users, you should leave all privileges in the user table set to 'N' and grant privileges at more specific levels only. You can grant privileges for particular databases, tables, columns, or routines.

The db table grants database-specific privileges. Values in the scope columns of this table can take the following forms:

- A blank User value matches the anonymous user. A nonblank value matches literally; there are no wildcards in user names.
- The wildcard characters "%" and "_" can be used in the Host and Db columns. These have the same meaning as for pattern-matching operations performed with the LIKE operator. If you want to use either character literally when granting privileges, you must escape it with a backslash. For example, to include the underscore character ("_") as part of a database name, specify it as "_" in the GRANT statement.
- A '%' or blank Host value means "any host."
- A '%' or blank Db value means "any database."

The server reads the db table into memory and sorts it at the same time that it reads the user table. The server sorts the db table based on the Host, Db, and User scope columns. As with the user table, sorting puts the most-specific values first and least-specific values last, and when the server looks for matching rows, it uses the first match that it finds.

The tables_priv, columns_priv, and procs_priv tables grant table-specific, column-specific, and routine-specific privileges. Values in the scope columns of these tables can take the following forms:

- The wildcard characters "%" and "_" can be used in the Host column. These have the same meaning as for pattern-matching operations performed with the LIKE operator.
- A '%' or blank Host value means "any host."

 The Db, Table_name, Column_name, and Routine_name columns cannot contain wildcards or be blank.

The server sorts the tables_priv, columns_priv, and procs_priv tables based on the Host, Db, and User columns. This is similar to db table sorting, but simpler because only the Host column can contain wildcards.

The server uses the sorted tables to verify each request that it receives. For requests that require administrative privileges such as SHUTDOWN or RELOAD, the server checks only the user table row because that is the only table that specifies administrative privileges. The server grants access if the row permits the requested operation and denies access otherwise. For example, if you want to execute mysqladmin shutdown but your user table row does not grant the SHUTDOWN privilege to you, the server denies access without even checking the db table. (It contains no Shutdown_priv column, so there is no need to do so.)

For database-related requests (INSERT, UPDATE, and so on), the server first checks the user's global privileges by looking in the user table row. If the row permits the requested operation, access is granted. If the global privileges in the user table are insufficient, the server determines the user's database-specific privileges by checking the db table:

The server looks in the db table for a match on the Host, Db, and User columns. The Host and User columns are matched to the connecting user's host name and MySQL user name. The Db column is matched to the database that the user wants to access. If there is no row for the Host and User, access is denied.

After determining the database-specific privileges granted by the db table rows, the server adds them to the global privileges granted by the user table. If the result permits the requested operation, access is granted. Otherwise, the server successively checks the user's table and column privileges in the tables_priv and columns_priv tables, adds those to the user's privileges, and permits or denies access based on the result. For stored-routine operations, the server uses the procs_priv table rather than tables_priv and columns_priv.

Expressed in boolean terms, the preceding description of how a user's privileges are calculated may be summarized like this:

```
global privileges
OR (database privileges AND host privileges)
OR table privileges
OR column privileges
OR routine privileges
```

It may not be apparent why, if the global user row privileges are initially found to be insufficient for the requested operation, the server adds those privileges to the database, table, and column privileges later. The reason is that a request might require more than one type of privilege. For example, if you execute an INSERT INTO ... SELECT statement, you need both the INSERT and the SELECT privileges. Your privileges might be such that the user table row grants one privilege and the db table row grants the other. In this case, you have the necessary privileges to perform the request, but the server cannot tell that from either table by itself; the privileges granted by the rows in both tables must be combined.

4.6 When Privilege Changes Take Effect

When mysqld starts, it reads all grant table contents into memory. The in-memory tables become effective for access control at that point.

If you modify the grant tables indirectly using account-management statements such as GRANT, REVOKE, SET PASSWORD, or RENAME USER, the server notices these changes and loads the grant tables into memory again immediately.

If you modify the grant tables directly using statements such as INSERT, UPDATE, or DELETE, your changes have no effect on privilege checking until you either restart the server or tell it to reload the tables. If you change the grant tables directly but forget to reload them, your changes have *no effect* until you restart the server. This may leave you wondering why your changes seem to make no difference!

To tell the server to reload the grant tables, perform a flush-privileges operation. This can be done by issuing a FLUSH PRIVILEGES statement or by executing a mysqladmin flush-privileges or mysqladmin reload command.

A grant table reload affects privileges for each existing client connection as follows:

- Table and column privilege changes take effect with the client's next request.
- Database privilege changes take effect the next time the client executes a USE db_name statement.

Note

Client applications may cache the database name; thus, this effect may not be visible to them without actually changing to a different database or flushing the privileges.

Global privileges and passwords are unaffected for a connected client. These changes take effect only
for subsequent connections.

If the server is started with the --skip-grant-tables option, it does not read the grant tables or implement any access control. Anyone can connect and do anything, which is insecure. To cause a server thus started to read the tables and enable access checking, flush the privileges.

4.7 Troubleshooting Problems Connecting to MySQL

If you encounter problems when you try to connect to the MySQL server, the following items describe some courses of action you can take to correct the problem.

Make sure that the server is running. If it is not, clients cannot connect to it. For example, if an attempt to
connect to the server fails with a message such as one of those following, one cause might be that the
server is not running:

```
shell> mysql
ERROR 2003: Can't connect to MySQL server on 'host_name' (111)
shell> mysql
ERROR 2002: Can't connect to local MySQL server through socket
'/tmp/mysql.sock' (111)
```

It might be that the server is running, but you are trying to connect using a TCP/IP port, named pipe, or
Unix socket file different from the one on which the server is listening. To correct this when you invoke
a client program, specify a --port option to indicate the proper port number, or a --socket option to
indicate the proper named pipe or Unix socket file. To find out where the socket file is, you can use this
command:

```
shell> netstat -ln | grep mysql
```

• Make sure that the server has not been configured to ignore network connections or (if you are attempting to connect remotely) that it has not been configured to listen only locally on its network interfaces. If the server was started with --skip-networking, it will not accept TCP/IP connections at all. If the server was started with --bind-address=127.0.0.1, it will listen for TCP/IP connections only locally on the loopback interface and will not accept remote connections.

- Check to make sure that there is no firewall blocking access to MySQL. Your firewall may be configured
 on the basis of the application being executed, or the port number used by MySQL for communication
 (3306 by default). Under Linux or Unix, check your IP tables (or similar) configuration to ensure that
 the port has not been blocked. Under Windows, applications such as ZoneAlarm or the Windows XP
 personal firewall may need to be configured not to block the MySQL port.
- The grant tables must be properly set up so that the server can use them for access control. For some distribution types (such as binary distributions on Windows, or RPM distributions on Linux), the installation process initializes the mysql database containing the grant tables. For distributions that do not do this, you must initialize the grant tables manually. For details, see Chapter 3, Postinstallation Setup and Testing.

To determine whether you need to initialize the grant tables, look for a mysql directory under the data directory. (The data directory normally is named data or var and is located under your MySQL installation directory.) Make sure that you have a file named user.MYD in the mysql database directory. If not, execute the mysql_install_db program. After running this program and starting the server, test the initial privileges by executing this command:

```
shell> mysql -u root
```

The server should let you connect without error.

 After a fresh installation, you should connect to the server and set up your users and their access permissions:

```
shell> mysql -u root mysql
```

The server should let you connect because the MySQL root user has no password initially. That is also a security risk, so setting the password for the root accounts is something you should do while you're setting up your other MySQL accounts. For instructions on setting the initial passwords, see Section 3.4, "Securing the Initial MySQL Accounts".

- If you have updated an existing MySQL installation to a newer version, did you run the
 mysql_upgrade script? If not, do so. The structure of the grant tables changes occasionally when
 new capabilities are added, so after an upgrade you should always make sure that your tables have the
 current structure. For instructions, see mysql_upgrade Check and Upgrade MySQL Tables.
- If a client program receives the following error message when it tries to connect, it means that the server expects passwords in a newer format than the client is capable of generating:

```
shell> mysql
Client does not support authentication protocol requested
by server; consider upgrading MySQL client
```

For information on how to deal with this, see Section 2.2.4, "Password Hashing in MySQL", and Client does not support authentication protocol.

• Remember that client programs use connection parameters specified in option files or environment variables. If a client program seems to be sending incorrect default connection parameters when you have not specified them on the command line, check any applicable option files and your environment. For example, if you get Access denied when you run a client without any options, make sure that you have not specified an old password in any of your option files!

You can suppress the use of option files by a client program by invoking it with the --no-defaults option. For example:

```
shell> mysqladmin --no-defaults -u root version
```

The option files that clients use are listed in Using Option Files. Environment variables are listed in Environment Variables.

If you get the following error, it means that you are using an incorrect root password:

```
shell> mysqladmin -u root -pxxxx ver
Access denied for user 'root'@'localhost' (using password: YES)
```

If the preceding error occurs even when you have not specified a password, it means that you have an incorrect password listed in some option file. Try the --no-defaults option as described in the previous item.

For information on changing passwords, see Section 5.5, "Assigning Account Passwords".

If you have lost or forgotten the root password, see How to Reset the Root Password.

If you change a password by using SET PASSWORD, INSERT, or UPDATE, you must encrypt the
password using the PASSWORD() function. If you do not use PASSWORD() for these statements, the
password will not work. For example, the following statement assigns a password, but fails to encrypt it,
so the user is not able to connect afterward:

```
SET PASSWORD FOR 'abe'@'host_name' = 'eagle';
```

Instead, set the password like this:

```
SET PASSWORD FOR 'abe'@'host_name' = PASSWORD('eagle');
```

The PASSWORD() function is unnecessary when you specify a password using the CREATE USER or GRANT statements or the mysqladmin password command. Each of those automatically uses PASSWORD() to encrypt the password. See Section 5.5, "Assigning Account Passwords", and CREATE USER Syntax.

• localhost is a synonym for your local host name, and is also the default host to which clients try to connect if you specify no host explicitly.

You can use a --host=127.0.0.1 option to name the server host explicitly. This will make a TCP/IP connection to the local mysqld server. You can also use TCP/IP by specifying a --host option that uses the actual host name of the local host. In this case, the host name must be specified in a user table row on the server host, even though you are running the client program on the same host as the server.

- The Access denied error message tells you who you are trying to log in as, the client host from which you are trying to connect, and whether you were using a password. Normally, you should have one row in the user table that exactly matches the host name and user name that were given in the error message. For example, if you get an error message that contains using password: No, it means that you tried to log in without a password.
- If you get an Access denied error when trying to connect to the database with mysql -u
 user_name, you may have a problem with the user table. Check this by executing mysql -u root
 mysql and issuing this SQL statement:

```
SELECT * FROM user;
```

The result should include a row with the Host and User columns matching your client's host name and your MySQL user name.

 If the following error occurs when you try to connect from a host other than the one on which the MySQL server is running, it means that there is no row in the user table with a Host value that matches the client host:

```
Host ... is not allowed to connect to this MySQL server
```

You can fix this by setting up an account for the combination of client host name and user name that you are using when trying to connect.

If you do not know the IP address or host name of the machine from which you are connecting, you should put a row with '%' as the Host column value in the user table. After trying to connect from the client machine, use a SELECT USER() query to see how you really did connect. Then change the '%' in the user table row to the actual host name that shows up in the log. Otherwise, your system is left insecure because it permits connections from any host for the given user name.

On Linux, another reason that this error might occur is that you are using a binary MySQL version that is compiled with a different version of the glibc library than the one you are using. In this case, you should either upgrade your operating system or glibc, or download a source distribution of MySQL version and compile it yourself. A source RPM is normally trivial to compile and install, so this is not a big problem.

 If you specify a host name when trying to connect, but get an error message where the host name is not shown or is an IP address, it means that the MySQL server got an error when trying to resolve the IP address of the client host to a name:

```
shell> mysqladmin -u root -pxxxx -h some_hostname ver
Access denied for user 'root'@'' (using password: YES)
```

If you try to connect as root and get the following error, it means that you do not have a row in the user table with a User column value of 'root' and that mysqld cannot resolve the host name for your client:

```
Access denied for user ''@'unknown'
```

These errors indicate a DNS problem. To fix it, execute <code>mysqladmin flush-hosts</code> to reset the internal DNS host cache. See DNS Lookup Optimization and the Host Cache.

Some permanent solutions are:

- Determine what is wrong with your DNS server and fix it.
- Specify IP addresses rather than host names in the MySQL grant tables.
- Put an entry for the client machine name in /etc/hosts on Unix or \windows\hosts on Windows.
- Start mysqld with the --skip-name-resolve option.
- Start mysqld with the --skip-host-cache option.

- On Unix, if you are running the server and the client on the same machine, connect to localhost. For connections to localhost, MySQL programs attempt to connect to the local server by using a Unix socket file, unless there are connection parameters specified to ensure that the client makes a TCP/IP connection. For more information, see Connecting to the MySQL Server.
- On Windows, if you are running the server and the client on the same machine and the server supports named pipe connections, connect to the host name. (period). Connections to . use a named pipe rather than TCP/IP.
- If mysql -u root works but mysql -h your_hostname -u root results in Access denied (where your_hostname is the actual host name of the local host), you may not have the correct name for your host in the user table. A common problem here is that the Host value in the user table row specifies an unqualified host name, but your system's name resolution routines return a fully qualified domain name (or vice versa). For example, if you have a row with host 'pluto' in the user table, but your DNS tells MySQL that your host name is 'pluto.example.com', the row does not work. Try adding a row to the user table that contains the IP address of your host as the Host column value. (Alternatively, you could add a row to the user table with a Host value that contains a wildcard; for example, 'pluto.%'. However, use of Host values ending with "%" is insecure and is not recommended!)
- If mysql -u user_name works but mysql -u user_name some_db does not, you have not granted access to the given user for the database named some_db.
- If mysql -u user_name works when executed on the server host, but mysql -h host_name -u user_name does not work when executed on a remote client host, you have not enabled access to the server for the given user name from the remote host.
- If you cannot figure out why you get Access denied, remove from the user table all rows that have Host values containing wildcards (rows that contain '%' or '_' characters). A very common error is to insert a new row with Host='%' and User='some_user', thinking that this enables you to specify localhost to connect from the same machine. The reason that this does not work is that the default privileges include a row with Host='localhost' and User=''. Because that row has a Host value 'localhost' that is more specific than '%', it is used in preference to the new row when connecting from localhost! The correct procedure is to insert a second row with Host='localhost' and User='some_user', or to delete the row with Host='localhost' and User=''. After deleting the row, remember to issue a FLUSH PRIVILEGES statement to reload the grant tables. See also Section 4.4, "Access Control, Stage 1: Connection Verification".
- If you are able to connect to the MySQL server, but get an Access denied message whenever you issue a SELECT ... INTO OUTFILE or LOAD DATA INFILE statement, your row in the user table does not have the FILE privilege enabled.
- If you change the grant tables directly (for example, by using INSERT, UPDATE, or DELETE statements) and your changes seem to be ignored, remember that you must execute a FLUSH PRIVILEGES statement or a mysqladmin flush-privileges command to cause the server to reload the privilege tables. Otherwise, your changes have no effect until the next time the server is restarted. Remember that after you change the root password with an UPDATE statement, you will not need to specify the new password until after you flush the privileges, because the server will not know you've changed the password yet!
- If your privileges seem to have changed in the middle of a session, it may be that a MySQL administrator has changed them. Reloading the grant tables affects new client connections, but it also affects existing connections as indicated in Section 4.6, "When Privilege Changes Take Effect".
- If you have access problems with a Perl, PHP, Python, or ODBC program, try to connect to the server with mysql -u user_name db_name or mysql -u user_name -pyour_pass db_name. If

you are able to connect using the <code>mysql</code> client, the problem lies with your program, not with the access privileges. (There is no space between <code>-p</code> and the password; you can also use the <code>--password=your_pass</code> syntax to specify the password. If you use the <code>-p</code> or <code>--password</code> option with no password value, MySQL prompts you for the password.)

- For testing purposes, start the mysqld server with the --skip-grant-tables option. Then you can change the MySQL grant tables and use the SHOW GRANTS statement to check whether your modifications have the desired effect. When you are satisfied with your changes, execute mysqladmin flush-privileges to tell the mysqld server to reload the privileges. This enables you to begin using the new grant table contents without stopping and restarting the server.
- If everything else fails, start the mysqld server with a debugging option (for example, -- debug=d, general, query). This prints host and user information about attempted connections, as well as information about each command issued. See The DBUG Package.
- If you have any other problems with the MySQL grant tables and feel you must post the problem to the mailing list, always provide a dump of the MySQL grant tables. You can dump the tables with the mysqldump mysql command. To file a bug report, see the instructions at How to Report Bugs or Problems. In some cases, you may need to restart mysqld with --skip-grant-tables to run mysqldump.

Chapter 5 MySQL User Account Management

Table of Contents

5.1 User Names and Passwords	. 59
5.2 Adding User Accounts	
5.3 Removing User Accounts	63
5.4 Setting Account Resource Limits	
5.5 Assigning Account Passwords	65
5.6 Password Expiration and Sandbox Mode	
5.7 Pluggable Authentication	69
5.8 Proxy Users	
5.9 Using Secure Connections	
5.9.1 OpenSSL Versus yaSSL	78
5.9.2 Building MySQL with Support for Secure Connections	79
5.9.3 Secure Connection Protocols and Ciphers	80
5.9.4 Configuring MySQL to Use Secure Connections	. 81
5.9.5 Command Options for Secure Connections	83
5.10 Creating SSL and RSA Certificates and Keys	86
5.10.1 Creating SSL Certificates and Keys Using openssl	
5.10.2 Creating RSA Keys Using openssl	92
5.11 Connecting to MySQL Remotely from Windows with SSH	92
5.12 SQL-Based MySQL Account Activity Auditing	93

This section describes how to set up accounts for clients of your MySQL server. It discusses the following topics:

- The meaning of account names and passwords as used in MySQL and how that compares to names and passwords used by your operating system
- · How to set up new accounts and remove existing accounts
- · How to change passwords
- · Guidelines for using passwords securely
- · How to use secure connections

See also Account Management Statements, which describes the syntax and use for all user-management SQL statements.

5.1 User Names and Passwords

MySQL stores accounts in the user table of the mysql system database. An account is defined in terms of a user name and the client host or hosts from which the user can connect to the server. For information about account representation in the user table, see Section 4.2, "Grant Tables".

The account may also have a password. MySQL supports authentication plugins, so it is possible that an account authenticates using some external authentication method. See Section 5.7, "Pluggable Authentication".

There are several distinctions between the way user names and passwords are used by MySQL and your operating system:

- User names, as used by MySQL for authentication purposes, have nothing to do with user names (login names) as used by Windows or Unix. On Unix, most MySQL clients by default try to log in using the current Unix user name as the MySQL user name, but that is for convenience only. The default can be overridden easily, because client programs permit any user name to be specified with a -u or -- user option. This means that anyone can attempt to connect to the server using any user name, so you cannot make a database secure in any way unless all MySQL accounts have passwords. Anyone who specifies a user name for an account that has no password is able to connect successfully to the server.
- MySQL user names can be up to 16 characters long. Operating system user names may be of a different maximum length. For example, Unix user names typically are limited to eight characters.

Warning

The limit on MySQL user name length is hardcoded in MySQL servers and clients, and trying to circumvent it by modifying the definitions of the tables in the mysql database *does not work*.

You should never alter the structure of tables in the <code>mysql</code> database in any manner whatsoever except by means of the procedure that is described in <code>mysql_upgrade</code> — Check and Upgrade MySQL Tables. Attempting to redefine MySQL's system tables in any other fashion results in undefined (and unsupported!) behavior. The server is free to ignore rows that become malformed as a result of such modifications.

• To authenticate client connections for accounts that use MySQL native authentication (implemented by the mysql_native_password authentication plugin), the server uses passwords stored in the user table. These passwords are distinct from passwords for logging in to your operating system. There is no necessary connection between the "external" password you use to log in to a Windows or Unix machine and the password you use to access the MySQL server on that machine.

If the server authenticates a client using some other plugin, the authentication method that the plugin implements may or may not use a password stored in the user table. In this case, it is possible that an external password is also used to authenticate to the MySQL server.

- Passwords stored in the user table are encrypted using plugin-specific algorithms. For information about MySQL native password hashing, see Section 2.2.4, "Password Hashing in MySQL".
- If the user name and password contain only ASCII characters, it is possible to connect to the server regardless of character set settings. To connect when the user name or password contain non-ASCII characters, the client should call the mysql_options() C API function with the MYSQL_SET_CHARSET_NAME option and appropriate character set name as arguments. This causes authentication to take place using the specified character set. Otherwise, authentication will fail unless the server default character set is the same as the encoding in the authentication defaults.

Standard MySQL client programs support a --default-character-set option that causes mysql_options() to be called as just described. In addition, character set autodetection is supported as described in Connection Character Sets and Collations. For programs that use a connector that is not based on the C API, the connector may provide an equivalent to mysql_options() that can be used instead. Check the connector documentation.

The preceding notes do not apply for ucs2, utf16, and utf32, which are not permitted as client character sets.

The MySQL installation process populates the grant tables with an initial account or accounts. The names and access privileges for these accounts are described in Section 3.4, "Securing the Initial MySQL Accounts", which also discusses how to assign passwords to them. Thereafter, you normally set up,

modify, and remove MySQL accounts using statements such as CREATE USER, DROP USER, GRANT, and REVOKE. See Account Management Statements.

To connect to a MySQL server with a command-line client, specify user name and password options as necessary for the account that you want to use:

```
shell> mysql --user=finley --password db_name
```

If you prefer short options, the command looks like this:

```
shell> mysql -u finley -p db_name
```

If you omit the password value following the --password or -p option on the command line (as just shown), the client prompts for one. Alternatively, the password can be specified on the command line:

```
shell> mysql --user=finley --password=password db_name
shell> mysql -u finley -ppassword db_name
```

If you use the -p option, there must be *no space* between -p and the following password value.

Specifying a password on the command line should be considered insecure. See Section 2.2.1, "End-User Guidelines for Password Security". You can use an option file or a login path file to avoid giving the password on the command line. See Using Option Files, and mysql_config_editor — MySQL Configuration Utility.

For additional information about specifying user names, passwords, and other connection parameters, see Connecting to the MySQL Server.

5.2 Adding User Accounts

You can create MySQL accounts two ways:

- By using account-management statements intended for creating accounts and establishing their
 privileges, such as CREATE USER and GRANT. These statements cause the server to make appropriate
 modifications to the underlying grant tables.
- By manipulating the MySQL grant tables directly with statements such as INSERT, UPDATE, or DELETE.

The preferred method is to use account-management statements because they are more concise and less error-prone than manipulating the grant tables directly. All such statements are described in Account Management Statements. Direct grant table manipulation is discouraged, and is not described here. The server is free to ignore rows that become malformed as a result of such modifications.

Another option for creating accounts is to use the GUI tool MySQL Workbench. Also, several third-party programs offer capabilities for MySQL account administration. phpMyAdmin is one such program.

The following examples show how to use the <code>mysql</code> client program to set up new accounts. These examples assume that privileges have been set up according to the defaults described in Section 3.4, "Securing the Initial MySQL Accounts". This means that to make changes, you must connect to the MySQL server as the MySQL <code>root</code> user, which has the <code>CREATE</code> USER privilege.

First, use the mysql program to connect to the server as the MySQL root user:

```
shell> mysql --user=root mysql
```

If you have assigned a password to the root account, you must also supply a --password or -p option.

After connecting to the server as root, you can add new accounts. The following example uses CREATE USER and GRANT statements to set up four accounts:

```
mysql> CREATE USER 'finley'@'localhost' IDENTIFIED BY 'some_pass';
mysql> GRANT ALL PRIVILEGES ON *.* TO 'finley'@'localhost'
    -> WITH GRANT OPTION;
mysql> CREATE USER 'finley'@'%' IDENTIFIED BY 'some_pass';
mysql> GRANT ALL PRIVILEGES ON *.* TO 'finley'@'%'
    -> WITH GRANT OPTION;
mysql> CREATE USER 'admin'@'localhost' IDENTIFIED BY 'admin_pass';
mysql> GRANT RELOAD,PROCESS ON *.* TO 'admin'@'localhost';
mysql> CREATE USER 'dummy'@'localhost';
```

The accounts created by those statements have the following properties:

• Two accounts have a user name of finley and a password of some_pass. Both are superuser accounts with full privileges to do anything. The 'finley'@'localhost' account can be used only when connecting from the local host. The 'finley'@'%' account uses the '%' wildcard for the host part, so it can be used to connect from any host.

The 'finley'@'localhost' account is necessary if there is an anonymous-user account for localhost. Without the 'finley'@'localhost' account, that anonymous-user account takes precedence when finley connects from the local host and finley is treated as an anonymous user. The reason for this is that the anonymous-user account has a more specific Host column value than the 'finley'@'%' account and thus comes earlier in the user table sort order. (user table sorting is discussed in Section 4.4, "Access Control, Stage 1: Connection Verification".)

- The 'admin'@'localhost' account has a password of admin_pass. This account can be used only by admin to connect from the local host. It is granted the RELOAD and PROCESS administrative privileges. These privileges enable the admin user to execute the mysqladmin reload, mysqladmin refresh, and mysqladmin flush-xxx commands, as well as mysqladmin processlist. No privileges are granted for accessing any databases. You could add such privileges using GRANT statements.
- The 'dummy'@'localhost' account has no password (which is insecure and not recommended). This account can be used only to connect from the local host. No privileges are granted. It is assumed that you will grant specific privileges to the account using GRANT statements.

To see the privileges for an account, use SHOW GRANTS:

The next examples create three accounts and grant them access to specific databases. Each of them has a user name of custom and password of obscure:

```
-> ON expenses.*
-> TO 'custom'@'host47.example.com';
mysql> CREATE USER 'custom'@'%.example.com' IDENTIFIED BY 'obscure';
mysql> GRANT SELECT,INSERT,UPDATE,DELETE,CREATE,DROP
-> ON customer.*
-> TO 'custom'@'%.example.com';
```

The three accounts can be used as follows:

- The first account can access the bankaccount database, but only from the local host.
- The second account can access the expenses database, but only from the host host47.example.com.
- The third account can access the customer database, from any host in the example.com domain. This account has access from all machines in the domain due to use of the "%" wildcard character in the host part of the account name.

5.3 Removing User Accounts

To remove an account, use the DROP USER statement, which is described in DROP USER Syntax. For example:

```
mysql> DROP USER 'jeffrey'@'localhost';
```

5.4 Setting Account Resource Limits

One means of restricting client use of MySQL server resources is to set the global max_user_connections system variable to a nonzero value. This limits the number of simultaneous connections that can be made by any given account, but places no limits on what a client can do once connected. In addition, setting max_user_connections does not enable management of individual accounts. Both types of control are of interest to MySQL administrators.

To address such concerns, MySQL permits limits for individual accounts on use of these server resources:

- The number of queries an account can issue per hour
- The number of updates an account can issue per hour
- The number of times an account can connect to the server per hour
- The number of simultaneous connections to the server by an account

Any statement that a client can issue counts against the query limit, unless its results are served from the query cache. Only statements that modify databases or tables count against the update limit.

An "account" in this context corresponds to a row in the <code>mysql.user</code> table. That is, a connection is assessed against the <code>User</code> and <code>Host</code> values in the <code>user</code> table row that applies to the connection. For example, an account <code>'usera'@'%.example.com'</code> corresponds to a row in the <code>user</code> table that has <code>User</code> and <code>Host</code> values of <code>usera</code> and <code>%.example.com</code>, to permit <code>usera</code> to connect from any host in the <code>example.com</code> domain. In this case, the server applies resource limits in this row collectively to all connections by <code>usera</code> from any host in the <code>example.com</code> domain because all such connections use the same account.

Before MySQL 5.0.3, an "account" was assessed against the actual host from which a user connects. This older method of accounting may be selected by starting the server with the --old-style-

user-limits option. In this case, if usera connects simultaneously from hostl.example.com and hostl.example.com, the server applies the account resource limits separately to each connection. If usera connects again from hostl.example.com, the server applies the limits for that connection together with the existing connection from that host.

To establish resource limits for an account, use the GRANT statement (see GRANT Syntax). Provide a WITH clause that names each resource to be limited. The default value for each limit is zero (no limit). For example, to create a new account that can access the customer database, but only in a limited fashion, issue these statements:

The limit types need not all be named in the WITH clause, but those named can be present in any order. The value for each per-hour limit should be an integer representing a count per hour. For MAX_USER_CONNECTIONS, the limit is an integer representing the maximum number of simultaneous connections by the account. If this limit is set to zero, the global max_user_connections system variable value determines the number of simultaneous connections. If max_user_connections is also zero, there is no limit for the account.

To modify limits for an existing account, use a GRANT USAGE statement at the global level (ON *.*). The following statement changes the query limit for francis to 100:

The statement modifies only the limit value specified and leaves the account otherwise unchanged.

To remove a limit, set its value to zero. For example, to remove the limit on how many times per hour francis can connect, use this statement:

As mentioned previously, the simultaneous-connection limit for an account is determined from the MAX_USER_CONNECTIONS limit and the max_user_connections system variable. Suppose that the global max_user_connections value is 10 and three accounts have individual resource limits specified as follows:

```
GRANT ... TO 'user1'@'localhost' WITH MAX_USER_CONNECTIONS 0;
GRANT ... TO 'user2'@'localhost' WITH MAX_USER_CONNECTIONS 5;
GRANT ... TO 'user3'@'localhost' WITH MAX_USER_CONNECTIONS 20;
```

user1 has a connection limit of 10 (the global max_user_connections value) because it has a MAX_USER_CONNECTIONS limit of zero. user2 and user3 have connection limits of 5 and 20, respectively, because they have nonzero MAX_USER_CONNECTIONS limits.

The server stores resource limits for an account in the user table row corresponding to the account. The max_questions, max_updates, and max_connections columns store the per-hour limits, and the max_user_connections column stores the MAX_USER_CONNECTIONS limit. (See Section 4.2, "Grant Tables".)

Resource-use counting takes place when any account has a nonzero limit placed on its use of any of the resources.

As the server runs, it counts the number of times each account uses resources. If an account reaches its limit on number of connections within the last hour, the server rejects further connections for the account until that hour is up. Similarly, if the account reaches its limit on the number of queries or updates, the server rejects further queries or updates until the hour is up. In all such cases, the server issues appropriate error messages.

Resource counting occurs per account, not per client. For example, if your account has a query limit of 50, you cannot increase your limit to 100 by making two simultaneous client connections to the server. Queries issued on both connections are counted together.

The current per-hour resource-use counts can be reset globally for all accounts, or individually for a given account:

- To reset the current counts to zero for all accounts, issue a FLUSH USER_RESOURCES statement.

 The counts also can be reset by reloading the grant tables (for example, with a FLUSH PRIVILEGES statement or a mysqladmin reload command).
- The counts for an individual account can be reset to zero by setting any of its limits again. Specify a limit value equal to the value currently assigned to the account.

Per-hour counter resets do not affect the MAX_USER_CONNECTIONS limit.

All counts begin at zero when the server starts. Counts do not carry over through server restarts.

For the MAX_USER_CONNECTIONS limit, an edge case can occur if the account currently has open the maximum number of connections permitted to it: A disconnect followed quickly by a connect can result in an error (ER_TOO_MANY_USER_CONNECTIONS or ER_USER_LIMIT_REACHED) if the server has not fully processed the disconnect by the time the connect occurs. When the server finishes disconnect processing, another connection will once more be permitted.

5.5 Assigning Account Passwords

Required credentials for clients that connect to the MySQL server can include a password. This section describes how to assign passwords for MySQL accounts.

MySQL stores passwords in the user table in the mysql system database. Operations that assign or modify passwords are permitted only to users with the CREATE USER privilege, or, alternatively, privileges for the mysql database (INSERT privilege to create new accounts, UPDATE privilege to modify existing accounts). If the read_only system variable is enabled, use of account-modification statements such as CREATE USER or SET PASSWORD additionally requires the SUPER privilege.

The discussion here summarizes syntax only for the most common password-assignment statements. For complete details on other possibilities, see CREATE USER Syntax, GRANT Syntax, and SET PASSWORD Syntax.

MySQL hashes passwords stored in the <code>mysql.user</code> table to obfuscate them. For most statements described here, MySQL automatically hashes the password specified. An exception is <code>SETPASSWORD('auth_string')</code>, for which you use the <code>PASSWORD()</code> function explicitly to hash the password. There are also syntaxes for <code>CREATE USER</code>, <code>GRANT</code>, and <code>SET PASSWORD</code> that permit hashed values to be specified literally; for details, see the descriptions of those statements.

MySQL uses plugins to perform client authentication; see Section 5.7, "Pluggable Authentication". The authentication plugin associated with an account determines the algorithm used to hash passwords for that account.

To assign a password when you create a new account, use CREATE USER and include an IDENTIFIED BY clause:

```
mysql> CREATE USER 'jeffrey'@'localhost'
    -> IDENTIFIED BY 'mypass';
```

For this CREATE USER syntax, MySQL automatically hashes the password before storing it in the mysql.user table.

CREATE USER also supports syntax for specifying the account authentication plugin. See CREATE USER Syntax.

To assign or change a password for an existing account, use one of the following methods:

Use SET PASSWORD with the PASSWORD() function:

```
mysql> SET PASSWORD FOR
    -> 'jeffrey'@'localhost' = PASSWORD('mypass');
```

If you are not connected as an anonymous user, you can change your own password by omitting the FOR clause:

```
mysql> SET PASSWORD = PASSWORD('mypass');
```

The PASSWORD() function hashes the password using the hashing method determined by the value of the old_passwords system variable value. If SET PASSWORD rejects the hashed password value returned by PASSWORD() as not being in the correct format, it may be necessary to change old_passwords to change the hashing method. See SET PASSWORD Syntax.

• Use a GRANT USAGE statement at the global level (ON *.*) to change an account password without affecting the account's current privileges:

```
mysql> GRANT USAGE ON *.* TO 'jeffrey'@'localhost'
    -> IDENTIFIED BY 'mypass';
```

For this GRANT syntax, MySQL automatically hashes the password before storing it in the mysql.user table.

To change an account password from the command line, use the mysqladmin command:

```
shell> mysqladmin -u user_name -h host_name password "new_password"
```

The account for which this command sets the password is the one with a mysql.user table row that matches user_name in the User column and the client host from which you connect in the Host column.

For password changes made using mysqladmin, MySQL automatically hashes the password before storing it in the mysql.user table.

5.6 Password Expiration and Sandbox Mode

MySQL 5.6 introduces password-expiration capability, to enable database administrators to expire account passwords and require users to reset their password. The immediately following discussion describes how password expiration works currently. Later, the development of this capability is detailed as it occurred

over several versions, as background to help you understand what features are available when. However, to ensure that you can take advantage of all features and fixes, you should use the most recent available version of MySQL if possible.

How Password Expiration Works

To expire an account password, use the ALTER USER statement. For example:

```
ALTER USER 'myuser'@'localhost' PASSWORD EXPIRE;
```

This statement modifies the row of the mysql.user table associated with the named account, setting the password_expired column to 'Y'. This does not affect any current connections the account has open. For each subsequent connection that uses the account, the server either disconnects the client or handles the client in "sandbox mode," in which the server permits to the client only those operations necessary to reset the expired password. The action taken by the server depends on both client and server settings.

If the server disconnects the client, it returns an ER_MUST_CHANGE_PASSWORD_LOGIN error:

```
shell> mysql -u myuser -p
Password: ******
ERROR 1862 (HY000): Your password has expired. To log in you must
change it using a client that supports expired passwords.
```

If the server puts the client in sandbox mode, these operations are permitted within the client session:

• The client can reset the account password with SET PASSWORD. This modifies the row of the mysql.user table associated with the current account, setting the password_expired column to 'N'. After the password has been reset, the server restores normal access for the session, as well as for subsequent connections that use the account.

It is possible to "reset" a password by setting it to its current value. As a matter of good policy, it is preferable to choose a different password.

• The client can use SET statements. This might be necessary prior to resetting the password; for example, if the account password uses a hashing format that requires the old_passwords system variable to be set to a value different from its default.

For any operation not permitted within the session, the server returns an ER_MUST_CHANGE_PASSWORD error:

```
mysql> USE performance_schema;

ERROR 1820 (HY000): You must SET PASSWORD before executing this statement

mysql> SELECT 1;

ERROR 1820 (HY000): You must SET PASSWORD before executing this statement
```

For noninteractive invocations of the <code>mysql</code> client (for example, in batch mode), the server normally disconnects the client if the password is expired. To permit <code>mysql</code> to stay connected so that the password can be changed (using the statements just described), add the <code>--connect-expired-password</code> option to the <code>mysql</code> command.

As mentioned previously, whether the server disconnects an expired-password client or puts it in sandbox mode depends on a combination of client and server settings. The following discussion describes the relevant settings and how they interact.

On the client side, a given client indicates whether it can handle sandbox mode for expired passwords. For clients that use the C client library, there are two ways to do this:

• Pass the MYSQL_OPT_CAN_HANDLE_EXPIRED_PASSWORDS flag to mysql_options() prior to connecting:

The mysql client enables MYSQL_OPT_CAN_HANDLE_EXPIRED_PASSWORDS if invoked interactively or the --connect-expired-password option is given.

• Pass the CLIENT_CAN_HANDLE_EXPIRED_PASSWORDS flag to mysql_real_connect() at connection time:

Other MySQL Connectors have their own conventions for indicating readiness to handle sandbox mode. See the relevant Connector documentation.

On the server side, if a client indicates that it can handle expired passwords, the server puts it in sandbox mode.

If a client does not indicate that it can handle expired passwords (or uses an older version of the client library that cannot so indicate), the server action depends on the value of the disconnect_on_expired_password system variable:

- If disconnect_on_expired_password is enabled (the default), the server disconnects the client with an ER MUST CHANGE PASSWORD LOGIN error.
- If disconnect on expired password is disabled, the server puts the client in sandbox mode.

The preceding client and server settings apply only for accounts with expired passwords. If a client connects using a nonexpired password, the server handles the client normally.

Development of Password-Expiration Capability

The following timeline describes the versions in which various password-expiration features were added.

MySQL 5.6.6: Initial implementation of password expiration.

The password_expired column is introduced in the mysql.user table to enable DBAs to expire account passwords. The column default value is 'N' (not expired).

The ALTER USER statement is introduced as the SQL interface for setting the password_expired column to 'Y'.

Connections that use an account with an expired password enter "sandbox mode" that permits only SET PASSWORD statements. For other statements, the server returns an ER_MUST_CHANGE_PASSWORD error. The intent is to force the client to reset the password before the server permits any other operations. SET PASSWORD resets the account password and sets password_expired to 'N'.

A bug in the initial implementation is that ALTER USER sets the Password column in the mysql.user table to the empty string. The implication is that users should wait until MySQL 5.6.7 to use this statement.

- MySQL 5.6.7: ALTER USER is fixed to not set the Password column to the empty string.
- MySQL 5.6.8: ALTER USER can be used as a prepared statement.

mysqladmin password is made capable of setting passwords for accounts with expired native or oldnative passwords.

Sandbox mode is changed to permit clients to execute SET statements in addition to SET PASSWORD Prohibiting SET prevented clients that needed to set old_passwords from resetting their password. It also broke some Connectors, which use SET extensively at connect time to initialize the session environment.

- MySQL 5.6.9: Sandbox mode is changed to permit SET PASSWORD only if the account named in the statement matches the account the client authenticated as.
- MySQL 5.6.10: Sandbox mode is changed to permit better control over how the server handles client
 connections for accounts with expired passwords, and to permit clients to signal whether they are
 capable of handling expired passwords:
 - The disconnect_on_expired_password system variable is added, which controls how the server treats expired-password accounts.
 - Two flags are added to the C API client library: MYSQL_OPT_CAN_HANDLE_EXPIRED_PASSWORDS for mysql_options() and CLIENT_CAN_HANDLE_EXPIRED_PASSWORDS for mysql_real_connect(). Each flag enables a client program to indicate whether it can handle sandbox mode for accounts with expired passwords.

MYSQL_OPT_CAN_HANDLE_EXPIRED_PASSWORDS is enabled for mysqltest unconditionally, for mysql in interactive mode, and for mysqladmin if the first command is password.

- The ER_MUST_CHANGE_PASSWORD_LOGIN error is added. The server returns this error when it disconnects a client.
- MySQL 5.6.12: The --connect-expired-password option is added to the mysql client to enable password-change statement execution in batch mode for accounts with an expired password.

Concurrent with these changes to sandbox mode in MySQL Server and the C API client library, work begins to modify Connectors for conformance to the changes.

5.7 Pluggable Authentication

When a client connects to the MySQL server, the server uses the user name provided by the client and the client host to select the appropriate account row from the mysql.user table. The server then authenticates the client, determining from the account row which authentication plugin applies for the client:

- If the account row specifies a plugin, the server invokes it to authenticate the user. If the server cannot find the plugin, an error occurs.
- If the account row specifies no plugin name, the server authenticates the account using either the mysql_native_password or mysql_old_password plugin, depending on whether the password hash value in the Password column used native hashing or the older pre-4.1 hashing method. Clients must match the password in the Password column of the account row.

The plugin returns a status to the server indicating whether the user is permitted to connect.

Pluggable authentication enables two important capabilities:

- External authentication: Pluggable authentication makes it possible for clients to connect to the MySQL server with credentials that are appropriate for authentication methods other than native authentication based on passwords stored in the mysql.user table. For example, plugins can be created to use external authentication methods such as PAM, Windows login IDs, LDAP, or Kerberos.
- **Proxy users:** If a user is permitted to connect, an authentication plugin can return to the server a user name different from the name of the connecting user, to indicate that the connecting user is a proxy for another user. While the connection lasts, the proxy user is treated, for purposes of access control, as having the privileges of a different user. In effect, one user impersonates another. For more information, see Section 5.8, "Proxy Users".

Several authentication plugins are available in MySQL:

- Plugins that perform native authentication that matches the password against the Password column of the account row. The mysql_native_password plugin implements authentication based on the native password hashing method. The mysql_old_password plugin implements native authentication based on the older (pre-4.1) password hashing method (and is now deprecated). See Section 6.1.1, "The Native Authentication Plugin", and Section 6.1.2, "The Old Native Authentication Plugin". Native authentication using mysql_native_password is the default for new accounts, unless the -- default-authentication-plugin option is set otherwise at server startup.
- A plugin that performs authentication using SHA-256 password hashing. This plugin matches the
 password against the authentication_string column of the account row. This is stronger
 encryption than that available with native authentication. See Section 6.1.4, "The SHA-256
 Authentication Plugin".
- A plugin that performs external authentication against PAM (Pluggable Authentication Modules), enabling MySQL Server to use PAM to authenticate MySQL users. This plugin supports proxy users as well. See Section 6.1.5, "The PAM Authentication Plugin".
- A plugin that performs external authentication on Windows, enabling MySQL Server to use native
 Windows services to authenticate client connections. Users who have logged in to Windows can
 connect from MySQL client programs to the server based on the information in their environment without
 specifying an additional password. This plugin supports proxy users as well. See Section 6.1.6, "The
 Windows Native Authentication Plugin".
- A client-side plugin that sends the password to the server without hashing or encryption. This plugin can be used by server-side plugins that require access to the password exactly as provided by the client user. See Section 6.1.7, "The Cleartext Client-Side Authentication Plugin".
- A plugin that authenticates clients that connect from the local host through the Unix socket file. See Section 6.1.8, "The Socket Peer-Credential Authentication Plugin".
- A test plugin that authenticates using MySQL native authentication. This plugin is intended for testing and development purposes, and as an example of how to write an authentication plugin. See Section 6.1.9, "The Test Authentication Plugin".

Note

For information about current restrictions on the use of pluggable authentication, including which connectors support which plugins, see Restrictions on Pluggable Authentication.

Third-party connector developers should read that section to determine the extent to which a connector can take advantage of pluggable authentication capabilities and what steps to take to become more compliant.

If you are interested in writing your own authentication plugins, see Writing Authentication Plugins.

Authentication Plugin Usage Instructions

This section provides general instructions for installing and using authentication plugins.

In general, pluggable authentication uses corresponding plugins on the server and client sides, so you use a given authentication method like this:

- On the server host, install the library containing the appropriate server plugin, if necessary, so that the server can use it to authenticate client connections. Similarly, on each client host, install the library containing the appropriate client plugin for use by client programs.
- Create MySQL accounts that specify use of the plugin for authentication.
- When a client connects, the server plugin tells the client program which client plugin to use for authentication.

The instructions here use an example authentication plugin included in MySQL distributions (see Section 6.1.9, "The Test Authentication Plugin"). The procedure is similar for other authentication plugins; substitute the appropriate plugin and file names.

The example authentication plugin has these characteristics:

- The server-side plugin name is test_plugin_server.
- The client-side plugin name is auth_test_plugin.
- Both plugins are located in the shared library file named auth_test_plugin.so in the plugin directory (the directory named by the plugin_dir system variable). The file name suffix might differ on your system.

Install and use the example authentication plugin as follows:

- 1. Make sure that the plugin library is installed on the server and client hosts.
- 2. Install the server-side test plugin at server startup or at runtime:
 - To install the plugin at startup, use the --plugin-load option. With this plugin-loading method, the option must be given each time you start the server. For example, use these lines in a my.cnf option file:

```
[mysqld]
plugin-load=test_plugin_server=auth_test_plugin.so
```

• To install the plugin at runtime, use the INSTALL PLUGIN statement:

```
INSTALL PLUGIN test_plugin_server SONAME 'auth_test_plugin.so';
```

This installs the plugin permanently and need be done only once.

3. Verify that the plugin is installed. For example, use SHOW PLUGINS:

```
Name: test_plugin_server
Status: ACTIVE
Type: AUTHENTICATION
Library: auth_test_plugin.so
License: GPL
```

For other ways to check the plugin, see Obtaining Server Plugin Information.

4. To specify that a MySQL user must be authenticated using a specific server plugin, name the plugin in the IDENTIFIED WITH clause of the CREATE USER statement that creates the user:

```
CREATE USER 'testuser'@'localhost' IDENTIFIED WITH test_plugin_server;
```

5. Connect to the server using a client program. The test plugin authenticates the same way as native MySQL authentication, so provide the usual --user and --password options that you normally use to connect to the server. For example:

```
shell> mysql --user=your_name --password=your_pass
```

For connections by testuser, the server sees that the account must be authenticated using the server-side plugin named test_plugin_server and communicates to the client program which client-side plugin it must use—in this case, auth_test_plugin.

In the case that the account uses the authentication method that is the default for both the server and the client program, the server need not communicate to the client which plugin to use, and a round trip in client/server negotiation can be avoided. This is true for accounts that use native MySQL authentication (mysql_native_password).

The --default-auth=plugin_name option can be specified on the mysql command line as a hint about which client-side plugin the program can expect to use, although the server will override this if the user account requires a different plugin.

If the client program does not find the plugin, specify a --plugin-dir=dir_name option to indicate where the plugin is located.

Note

If you start the server with the <code>--skip-grant-tables</code> option, authentication plugins are not used even if loaded because the server performs no client authentication and permits any client to connect. Because this is insecure, you might want to use <code>--skip-grant-tables</code> in conjunction with <code>--skip-networking</code> to prevent remote clients from connecting.

5.8 Proxy Users

Authentication to the MySQL server occurs by means of authentication plugins. The plugin that authenticates a given connection may request that the connecting (external) user be treated as a different user for privilege-checking purposes. This enables the external user to be a proxy for the second user; that is, to have the privileges of the second user:

- The external user is a "proxy user" (a user who can impersonate or become known as another user).
- The second user is a "proxied user" (a user whose identity can be taken on by a proxy user).

This section describes how the proxy user capability works. For general information about authentication plugins, see Section 5.7, "Pluggable Authentication". For information about specific plugins, see

Section 6.1, "Authentication Plugins". For information about writing authentication plugins that support proxy users, see Implementing Proxy User Support in Authentication Plugins.

For proxying to occur for a given authentication plugin, these conditions must be satisfied:

- A proxy user account must be set up to be authenticated by the plugin. Use the CREATE USER or GRANT statement to associate an account with a plugin.
- For a client connecting to the proxy account to be treated as a proxy user, the plugin must return a user name different from the client user name, to indicate the user name for the proxied account.
- The proxy user account must have the PROXY privilege for the proxied account. Use the GRANT statement for this.

The proxy mechanism permits mapping only the client user name to the proxied user name. There is no provision for mapping host names. When a connecting client matches a proxy account, the server attempts to find a match for a proxied account using the user name returned by the authentication plugin and the host name of the proxy account.

Consider the following definitions:

```
-- create proxy user

CREATE USER 'employee_ext'@'localhost'
   IDENTIFIED WITH my_auth_plugin AS 'my_auth_string';
-- create proxied user

CREATE USER 'employee'@'localhost'
   IDENTIFIED BY 'employee_pass';
-- grant PROXY privilege for proxy user to proxied user

GRANT PROXY
   ON 'employee'@'localhost'
   TO 'employee_ext'@'localhost';
```

When a client connects as <code>employee_ext</code> from the local host, <code>MySQL</code> uses <code>my_auth_plugin</code> to perform authentication. Suppose that <code>my_auth_plugin</code> returns a user name of <code>employee</code> to the server, based on the content of <code>'my_auth_string'</code> and perhaps by consulting some external authentication system. The name <code>employee</code> differs from <code>employee_ext</code>, so returning <code>employee</code> serves as a request to the server to treat the <code>employee_ext</code> client, for purposes of privilege checking, as the <code>employee</code> local user.

In this case, <code>employee_ext</code> is the proxy user and <code>employee</code> is the proxied user.

The server verifies that proxy authentication for <code>employee</code> is possible for the <code>employee_ext</code> user by checking whether <code>employee_ext</code> (the proxy user) has the <code>PROXY</code> privilege for <code>employee</code> (the proxied user). If this privilege has not been granted, an error occurs.

When proxying occurs, the USER() and CURRENT_USER() functions can be used to see the difference between the connecting user (the proxy user) and the account whose privileges apply during the current session (the proxied user). For the example just described, those functions return these values:

In the CREATE USER statement that creates the proxy user account, the IDENTIFIED WITH clause that names the authentication plugin is optionally followed by an AS 'auth_string' clause specifying

a string that the server passes to the plugin when the user connects. If present, the string provides information that helps the plugin determine how to map the external client user name to a proxied user name. It is up to each plugin whether it requires the AS clause. If so, the format of the authentication string depends on how the plugin intends to use it. Consult the documentation for a given plugin for information about the authentication string values it accepts.

Granting the Proxy Privilege

The PROXY privilege is needed to enable an external user to connect as and have the privileges of another user. To grant this privilege, use the GRANT statement. For example:

```
GRANT PROXY ON 'proxied_user' TO 'proxy_user';
```

The statement creates a row in the mysql.proxies_priv grant table.

At connection time, *proxy_user* must represent a valid externally authenticated MySQL user, and *proxied_user* must represent a valid locally authenticated user. Otherwise, the connection attempt fails.

The corresponding REVOKE syntax is:

```
REVOKE PROXY ON 'proxied_user' FROM 'proxy_user';
```

MySQL GRANT and REVOKE syntax extensions work as usual. For example:

```
GRANT PROXY ON 'a' TO 'b', 'c', 'd';

GRANT PROXY ON 'a' TO 'd' IDENTIFIED BY ...;

GRANT PROXY ON 'a' TO 'd' WITH GRANT OPTION;

GRANT PROXY ON 'a' TO ''@'';

REVOKE PROXY ON 'a' FROM 'b', 'c', 'd';
```

In the preceding example, ''@'' is the default proxy user and means "any user." Default proxy user are discussed in Default Proxy Users.

The PROXY privilege can be granted in these cases:

- By a user that has GRANT PROXY ... WITH GRANT OPTION for proxied_user.
- By proxied_user for itself: The value of USER() must exactly match CURRENT_USER() and proxied_user, for both the user name and host name parts of the account name.

The initial root account created during MySQL installation has the PROXY ... WITH GRANT OPTION privilege for ''@'', that is, for all users and all hosts. This enables root to set up proxy users, as well as to delegate to other accounts the authority to set up proxy users. For example, root can do this:

```
CREATE USER 'admin'@'localhost' IDENTIFIED BY 'test';
GRANT PROXY ON ''@'' TO 'admin'@'localhost' WITH GRANT OPTION;
```

Those statements create an admin user that can manage all GRANT PROXY mappings. For example, admin can do this:

```
GRANT PROXY ON sally TO joe;
```

Default Proxy Users

To specify that some or all users should connect using a given authentication plugin, create a "blank" MySQL user, associate it with that plugin for authentication, and let the plugin return the real authenticated user name (if different from the blank user). For example, suppose that there exists a plugin named ldap_auth that implements LDAP authentication and maps connecting users onto either a developer or manager account. To set up proxying of users onto these accounts, use the following statements:

```
-- create default proxy user

CREATE USER ''@'' IDENTIFIED WITH ldap_auth AS 'O=Oracle, OU=MySQL';
-- create proxied users

CREATE USER 'developer'@'localhost' IDENTIFIED BY 'developer_pass';

CREATE USER 'manager'@'localhost' IDENTIFIED BY 'manager_pass';
-- grant PROXY privilege for default proxy user to proxied users

GRANT PROXY ON 'manager'@'localhost' TO ''@'';

GRANT PROXY ON 'developer'@'localhost' TO ''@'';
```

Now assume that a client tries to connect as follows:

```
mysql --user=myuser --password='myuser_pass' ...
```

The server will not find myuser defined as a MySQL user. But because there is a blank user account (''@''), that matches the client user name and host name, the server authenticates the client against that account: The server invokes the ldap_auth authentication plugin and passes myuser and myuser_pass to it as the user name and password.

If the ldap_auth plugin finds in the LDAP directory that myuser_pass is not the correct password for myuser, authentication fails and the server rejects the connection.

If the password is correct and <code>ldap_auth</code> finds that <code>myuser</code> is a developer, it returns the user name <code>developer</code> to the MySQL server, rather than <code>myuser</code>. Returning a user name different from the client user name of <code>myuser</code> signals to the server that it should treat <code>myuser</code> as a proxy. The server verifies that <code>''@''</code> can authenticate as <code>developer</code> (because it has the <code>PROXY</code> privilege to do so) and accepts the connection. The session proceeds with <code>myuser</code> having the privileges of <code>developer</code>, the proxied user. (These privileges should be set up by the DBA using <code>GRANT</code> statements, not shown.) The <code>USER()</code> and <code>CURRENT_USER()</code> functions return these values:

If the plugin instead finds in the LDAP directory that myuser is a manager, it returns manager as the user name and the session proceeds with myuser having the privileges of manager.

For simplicity, external authentication cannot be multilevel: Neither the credentials for developer nor those for manager are taken into account in the preceding example. However, they are still used if a client tries to connect and authenticate directly as the developer or manager account, which is why those accounts should be assigned passwords.

Default Proxy User and Anonymous User Conflicts

If you intend to create a default proxy user, check for other existing "match any user" accounts that take precedence over the default proxy user and thus prevent that user from working as intended.

In the preceding discussion, the default proxy user account has '' in the host part, which matches any host. If you set up a default proxy user, take care to also check whether nonproxy accounts exist with the same user part and '%' in the host part, because '%' also matches any host, but has precedence over '' by the rules that the server uses to sort account rows internally (see Section 4.4, "Access Control, Stage 1: Connection Verification").

Suppose that a MySQL installation includes these two accounts:

```
-- create default proxy user

CREATE USER ''@''

IDENTIFIED WITH some_plugin AS 'some_auth_string';

-- create anonymous user

CREATE USER ''@'%'

IDENTIFIED BY 'some_password';
```

The first account (''@'') is intended as the default proxy user, used to authenticate connections for users who do not otherwise match a more-specific account. The second account (''@'%') is an anonymous-user account, which might have been created, for example, to enable users without their own account to connect anonymously.

Both accounts have the same user part (''), which matches any user. And each account has a host part that matches any host. Nevertheless, there is a priority in account matching for connection attempts because the matching rules sort a host of '%' ahead of ''. For accounts that do not match any more-specific account, the server attempts to authenticate them against ''@'%' (the anonymous user) rather than ''@'' (the default proxy user). The result is that the default proxy account is never used.

To avoid this problem, use one of the following strategies:

- Remove the anonymous account so that it does not conflict with the default proxy user. This might be a good idea anyway if you want to associate every connection with a named user.
- Use a more-specific default proxy user that matches ahead of the anonymous user. For example, to permit only localhost proxy connections, use ''@'localhost':

```
CREATE USER ''@'localhost'
IDENTIFIED WITH some_plugin AS 'some_auth_string';
```

In addition, modify any GRANT PROXY statements to name ''@'localhost' rather than ''@'' as the proxy user.

Be aware that this strategy prevents anonymous-user connections from localhost.

 Create multiple proxy users, one for local connections and one for "everything else" (remote connections). This can be useful particularly when local users should have different privileges from remote users.

Create the proxy users:

```
-- create proxy user for local connections
CREATE USER ''@'localhost'
```

```
IDENTIFIED WITH some_plugin AS 'some_auth_string';
-- create proxy user for remote connections
CREATE USER ''@'%'
IDENTIFIED WITH some_plugin AS 'some_auth_string';
```

Create the proxied users:

```
-- create proxied user for local connections

CREATE USER 'developer'@'localhost'

IDENTIFIED BY 'some_password';

-- create proxied user for remote connections

CREATE USER 'developer'@'%'

IDENTIFIED BY 'some_password';
```

Grant the proxy privilege to each proxy user for the corresponding proxied user:

```
GRANT PROXY ON 'developer'@'localhost' TO ''@'localhost';
GRANT PROXY ON 'developer'@'%' TO ''@'%';
```

Finally, grant appropriate privileges to the local and remote proxied users (not shown).

Assume that the <code>some_plugin/'some_auth_string'</code> combination causes <code>some_plugin</code> to map the client user name to <code>developer</code>. Local connections match the <code>''@'localhost'</code> proxy user, which maps to the <code>'developer'@'localhost'</code> proxied user. Remote connections match the <code>''@'%'</code> proxy user, which maps to the <code>'developer'@'%'</code> proxied user.

Proxy User System Variables

Two system variables help trace the proxy login process:

• proxy_user: This value is NULL if proxying is not used. Otherwise, it indicates the proxy user account. For example, if a client authenticates through the ''@'' proxy account, this variable is set as follows:

external_user: Sometimes the authentication plugin may use an external user to authenticate to the
MySQL server. For example, when using Windows native authentication, a plugin that authenticates
using the windows API does not need the login ID passed to it. However, it still uses a Windows user
ID to authenticate. The plugin may return this external user ID (or the first 512 UTF-8 bytes of it) to the
server using the external_user read-only session variable. If the plugin does not set this variable, its
value is NULL.

5.9 Using Secure Connections

With an unencrypted connection between the MySQL client and the server, someone with access to the network could watch all your traffic and inspect the data being sent or received between client and server.

When you must move information over a network in a secure fashion, an unencrypted connection is unacceptable. To make any kind of data unreadable, use encryption. Encryption algorithms must include security elements to resist many kinds of known attacks such as changing the order of encrypted messages or replaying data twice.

MySQL supports secure (encrypted) connections between clients and the server using the TLS (Transport Layer Security) protocol. TLS is sometimes referred to as SSL (Secure Sockets Layer) but MySQL does not actually use the SSL protocol for secure connections because it provides weak encryption (see Section 5.9.3, "Secure Connection Protocols and Ciphers").

TLS uses encryption algorithms to ensure that data received over a public network can be trusted. It has mechanisms to detect data change, loss, or replay. TLS also incorporates algorithms that provide identity verification using the X509 standard.

X509 makes it possible to identify someone on the Internet. In basic terms, there should be some entity called a "Certificate Authority" (or CA) that assigns electronic certificates to anyone who needs them. Certificates rely on asymmetric encryption algorithms that have two encryption keys (a public key and a secret key). A certificate owner can present the certificate to another party as proof of identity. A certificate consists of its owner's public key. Any data encrypted using this public key can be decrypted only using the corresponding secret key, which is held by the owner of the certificate.

MySQL can be compiled for secure-connection support using OpenSSL or yaSSL. For a comparison of the two packages, see Section 5.9.1, "OpenSSL Versus yaSSL" For information about the encryption protocols and ciphers each package supports, see Section 5.9.3, "Secure Connection Protocols and Ciphers".

MySQL performs encryption on a per-connection basis, and use of encryption for a given user can be optional or mandatory. This enables you to choose an encrypted or unencrypted connection according to the requirements of individual applications. For information on how to require users to use encrypted connections, see the discussion of the REQUIRE clause of the GRANT statement in GRANT Syntax.

Encrypted connections are not used by default. For applications that require the security provided by encrypted connections, the extra computation to encrypt the data is worthwhile.

Secure connections are available through the MySQL C API using the $mysql_sel_sel()$ and $mysql_options()$ functions. See $mysql_sel()$, and $mysql_options()$.

Replication uses the C API, so secure connections can be used between master and slave servers. See Setting Up Replication to Use Secure Connections.

It is also possible to connect securely from within an SSH connection to the MySQL server host. For an example, see Section 5.11, "Connecting to MySQL Remotely from Windows with SSH".

5.9.1 OpenSSL Versus yaSSL

MySQL can be compiled using OpenSSL or yaSSL, both of which enable secure conections based on the OpenSSL API:

- MySQL Enterprise Edition binary distributions are compiled using OpenSSL. It is not possible to use yaSSL with MySQL Enterprise Edition.
- · MySQL Community Edition binary distributions are compiled using yaSSL.
- MySQL Community Edition source distributions can be compiled using either OpenSSL or yaSSL (see Section 5.9.2, "Building MySQL with Support for Secure Connections").

OpenSSL and yaSSL offer the same basic functionality, but MySQL distributions compiled using OpenSSL have additional features:

• OpenSSL supports a wider range of encryption ciphers from which to choose for the --ssl-cipher option. OpenSSL supports the --ssl-capath, --ssl-crl, and --ssl-crlpath options. See Section 5.9.5, "Command Options for Secure Connections".

- Accounts that authenticate using the sha256_password plugin can use RSA key files for secure password exchange over unencrypted connections. See Section 6.1.4, "The SHA-256 Authentication Plugin".
- OpenSSL supports more encryption modes for the AES_ENCRYPT() and AES_DECRYPT() functions. See Encryption and Compression Functions

Certain OpenSSL-related system and status variables are present only if MySQL was compiled using OpenSSL:

- sha256_password_private_key_path (added in MySQL 5.6.6)
- sha256_password_public_key_path (added in MySQL 5.6.6)
- Rsa public key (added in MySQL 5.6.6)

To determine whether your server was compiled using OpenSSL, test the existence of any of those variables. For example, this statement returns a row if OpenSSL was used and an empty result if yaSSL was used:

```
SHOW STATUS LIKE 'Rsa_public_key';
```

Such tests assume that your server version is not older than the first appearance of the variable tested. For example, you cannot test for Rsa_public_key before MySQL 5.6.6.

5.9.2 Building MySQL with Support for Secure Connections

To use SSL connections between the MySQL server and client programs, your system must support either OpenSSL or yaSSL:

- MySQL Enterprise Edition binary distributions are compiled using OpenSSL. It is not possible to use yaSSL with MySQL Enterprise Edition.
- MySQL Community Edition binary distributions are compiled using yaSSL.
- MySQL Community Edition source distributions can be compiled using either OpenSSL or yaSSL.

If you compile MySQL from a source distribution, CMake configures the distribution to use yaSSL by default. To compile using OpenSSL instead, use this procedure:

 Ensure OpenSSL 1.0.1 or higher is installed on your system. To obtain OpenSSL, visit http:// www.openssl.org.

If the installed OpenSSL version is lower than 1.0.1, CMake produces an error at MySQL configuration time.

2. To use OpenSSL, add the -DWITH_SSL=system option to the CMake command you normally use to configure the MySQL source distribution. For example:

```
shell> cmake . -DWITH_SSL=system
```

That command configures the distribution to use the installed OpenSSL library. Alternatively, to explicitly specify the path name to the OpenSSL installation, use the following syntax. This can be useful if you have multiple versions of OpenSSL installed, to prevent CMake from choosing the wrong one:

```
shell> cmake . -DWITH_SSL=path_name
```

See MySQL Source-Configuration Options.

3. Compile and install the distribution.

To check whether a mysqld server supports secure connections, examine the value of the have_ssl system variable:

If the value is YES, the server supports secure connections. If the value is DISABLED, the server is capable of supporting secure connections but was not started with the appropriate --ssl-xxx options to enable secure connections to be used; see Section 5.9.4, "Configuring MySQL to Use Secure Connections".

To determine whether a server was compiled using OpenSSL or yaSSL, check the existence of any of the system or status variables that are present only for OpenSSL. See Section 5.9.1, "OpenSSL Versus yaSSL"

5.9.3 Secure Connection Protocols and Ciphers

To determine which encryption protocol and cipher are in use for an encrypted connection, use the following statements to check the values of the Ssl_version and Ssl_cipher status variables:

If the connection is not encrypted, both variables have an empty value.

MySQL supports encrypted connections using the TLSv1 protocol. As of MySQL 5.6.23, it explicitly disables SSL 2.0 and SSL 3.0 because they provide weak encryption.

To determine which ciphers a given server supports, use the following statement to check the value of the Ssl_cipher_list status variable:

```
SHOW SESSION STATUS LIKE 'Ssl_cipher_list';
```

The set of available ciphers depends on your MySQL version and whether MySQL was compiled using OpenSSL or yaSSL, and (for OpenSSL) the library version used to compile MySQL.

MySQL passes this cipher list to OpenSSL:

```
AES256-GCM-SHA384
```

```
AES256-SHA
AES256-SHA256
CAMELLIA256-SHA
DES-CBC3-SHA
DHE-DSS-AES256-GCM-SHA384
DHE-DSS-AES256-SHA
DHE-DSS-AES256-SHA256
DHE-DSS-CAMELLIA256-SHA
DHE-RSA-AES256-GCM-SHA384
DHE-RSA-AES256-SHA
DHE-RSA-AES256-SHA256
DHE-RSA-CAMELLIA256-SHA
ECDH-ECDSA-AES256-GCM-SHA384
ECDH-ECDSA-AES256-SHA
ECDH-ECDSA-AES256-SHA384
ECDH-ECDSA-DES-CBC3-SHA
ECDH-RSA-AES256-GCM-SHA384
ECDH-RSA-AES256-SHA
ECDH-RSA-AES256-SHA384
ECDH-RSA-DES-CBC3-SHA
ECDHE-ECDSA-AES128-GCM-SHA256
ECDHE-ECDSA-AES128-SHA
ECDHE-ECDSA-AES128-SHA256
ECDHE-ECDSA-AES256-GCM-SHA384
ECDHE-ECDSA-AES256-SHA
ECDHE-ECDSA-AES256-SHA384
ECDHE-ECDSA-DES-CBC3-SHA
ECDHE-RSA-AES128-GCM-SHA256
ECDHE-RSA-AES128-SHA
ECDHE-RSA-AES128-SHA256
ECDHE-RSA-AES256-GCM-SHA384
ECDHE-RSA-AES256-SHA
ECDHE-RSA-AES256-SHA384
ECDHE-RSA-DES-CBC3-SHA
EDH-DSS-DES-CBC3-SHA
EDH-RSA-DES-CBC3-SHA
PSK-3DES-EDE-CBC-SHA
PSK-AES256-CBC-SHA
SRP-DSS-3DES-EDE-CBC-SHA
SRP-DSS-AES-128-CBC-SHA
SRP-DSS-AES-256-CBC-SHA
SRP-RSA-3DES-EDE-CBC-SHA
SRP-RSA-AES-128-CBC-S
SRP-RSA-AES-256-CBC-SHA
```

MySQL passes this cipher list to yaSSL:

```
AES128-RMD
AES128-SHA
AES256-RMD
AES256-SHA
DES-CBC-SHA
DES-CBC3-RMD
DES-CBC3-SHA
DHE-RSA-AES128-RMD
DHE-RSA-AES128-SHA
DHE-RSA-AES256-RMD
DHE-RSA-AES256-SHA
DHE-RSA-DES-CBC3-RMD
EDH-RSA-DES-CBC-SHA
EDH-RSA-DES-CBC3-SHA
RC4-MD5
RC4-SHA
```

5.9.4 Configuring MySQL to Use Secure Connections

To enable secure connections, your MySQL distribution must be built with SSL support, as described in Section 5.9.2, "Building MySQL with Support for Secure Connections". In addition, the proper options must be used to specify the appropriate certificate and key files. For a complete list of options related to establishment of secure connections, see Section 5.9.5, "Command Options for Secure Connections".

If you need to create the required certificate and key files, see Section 5.10, "Creating SSL and RSA Certificates and Keys".

Server-Side Configuration for Secure Connections

To start the MySQL server so that it permits clients to connect securely, use options that identify the certificate and key files the server uses when establishing a secure connection:

- --ssl-ca identifies the Certificate Authority (CA) certificate.
- --ssl-cert identifies the server public key certificate. This can be sent to the client and authenticated against the CA certificate that it has.
- --ssl-key identifies the server private key.

For example, start the server with these lines in the my.cnf file, changing the file names as necessary:

```
[mysqld]
ssl-ca=ca.pem
ssl-cert=server-cert.pem
ssl-key=server-key.pem
```

Each option names a file in PEM format. If you have a MySQL source distribution, you can test your setup using the demonstration certificate and key files in its mysql-test/std_data directory.

Client-Side Configuration for Secure Connections

For client programs, options for secure connections are similar to those used on the server side, but --ssl-cert and --ssl-key identify the client public and private key:

- --ssl-ca identifies the Certificate Authority (CA) certificate. This option, if used, must specify the same certificate used by the server.
- --ssl-cert identifies the client public key certificate.
- --ssl-key identifies the client private key.

To connect securely to a MySQL server that supports secure connections, the options that a client must specify depend on the encryption requirements of the MySQL account used by the client. (See the discussion of the REQUIRE clause in GRANT Syntax.)

Suppose that you want to connect using an account that has no special encryption requirements or was created using a GRANT statement that includes the REQUIRE SSL option. As a recommended set of secure-connection options, start the server with at least --ssl-cert and --ssl-key, and invoke the client with --ssl-ca. A client can connect securely like this:

```
shell> mysql --ssl-ca=ca.pem
```

To require that a client certificate also be specified, create the account using the REQUIRE X509 option. Then the client must also specify the proper client key and certificate files or the server will reject the connection:

```
shell> mysql --ssl-ca=ca.pem \
    --ssl-cert=client-cert.pem \
    --ssl-key=client-key.pem
```

To prevent use of encryption and override other --ssl-xxx options, invoke the client program with --ssl=0 or a synonym (--skip-ssl, --disable-ssl):

```
shell> mysql --ssl=0
```

A client can determine whether the current connection with the server uses encryption by checking the value of the Ssl_cipher status variable. If the value is empty, the connection is encrypted. Otherwise, the connection is encrypted and the value indicates the encryption cipher. For example:

For the <code>mysql</code> client, an alternative is to use the <code>STATUS</code> or <code>\s</code> command and check the <code>SSL</code> line:

```
mysql> \s
...
SSL: Cipher in use is DHE-RSA-AES256-SHA
...
```

Or:

```
mysql> \s ...
SSL: Not in use ...
```

C API Configuration for Secure Connections

The C API enables application programs to use secure connections:

- To establish a secure connection, use the mysql_ssl_set() C API function to set the appropriate certificate options before calling mysql_real_connect(). See mysql_ssl_set().
- To determine whether encryption is in use after the connection is established, use
 mysql_get_ssl_cipher(). A non-NULL return value indicates an encrypted connection and names
 the cipher used for encryption. A NULL return value indicates that encryption is not being used. See
 mysql_get_ssl_cipher().

Replication uses the C API, so secure connections can be used between master and slave servers. See Setting Up Replication to Use Secure Connections.

5.9.5 Command Options for Secure Connections

This section describes options that specify whether to use secure connections and the names of certificate and key files. These options can be given on the command line or in an option file. They are not available unless MySQL has been built with SSL support. See Section 5.9.2, "Building MySQL with Support for

Secure Connections". For examples of suggested use and how to check whether a connection is secure, see Section 5.9.4, "Configuring MySQL to Use Secure Connections".

Table 5.1 Secure-Connection Option Summary

Format	Description	Introduced
skip-ssl	Do not use secure connection	
ssl	Enable secure connection	
ssl-ca	Path of file that contains list of trusted SSL CAs	
ssl-capath	Path of directory that contains trusted SSL CA certificates in PEM format	
ssl-cert	Path of file that contains X509 certificate in PEM format	
ssl-cipher	List of permitted ciphers to use for connection encryption	
ssl-crl	Path of file that contains certificate revocation lists	5.6.3
ssl-crlpath	Path of directory that contains certificate revocation list files	5.6.3
ssl-key	Path of file that contains X509 key in PEM format	
ssl-mode	Security state of connection to server	5.6.30
ssl-verify-server-cert	Verify server certificate Common Name value against host name used when connecting to server	

• --ssl

For the MySQL server, this option specifies that the server permits but does not require secure connections.

For MySQL client programs, this option permits but does not require the client to connect to the server using encryption. Therefore, this option is not sufficient in itself to cause a secure connection to be used. For example, if you specify this option for a client program but the server has not been configured to support secure connections, the client falls back to an unencrypted connection.

As a recommended set of options to enable secure connections, use at least --ssl-cert and --ssl-key on the server side and --ssl-ca on the client side. See Section 5.9.4, "Configuring MySQL to Use Secure Connections".

--ssl may be implied by other --ssl-xxx options, as indicated in the descriptions for those options.

The <code>--ssl</code> option in negated form overrides other <code>--ssl-xxx</code> options and indicates that encryption should <code>not</code> be used. To do this, specify the option as <code>--ssl=0</code> or a synonym (<code>--skip-ssl</code>, <code>--disable-ssl</code>). For example, you might have options specified in the <code>[client]</code> group of your option file to use secure connections by default when you invoke MySQL client programs. To use an unencrypted connection instead, invoke the client program with <code>--ssl=0</code> on the command line to override the options in the option file.

To require use of secure connections by a MySQL account, use a GRANT statement for the account that includes at least a REQUIRE SSL clause. Connections for the account will be rejected unless MySQL supports secure connections and the server and client have been started with the proper secure-connection options.

The REQUIRE clause permits other encryption-related options, which can be used to enforce stricter requirements than REQUIRE SSL. For additional details about which command options may or must be specified by clients that connect using accounts configured using the various REQUIRE options, see the description of REQUIRE in GRANT Syntax.

• --ssl-ca=file_name

The path to a file in PEM format that contains a list of trusted SSL certificate authorities. This option implies --ss1.

If you use encryption when establishing a client connection, to tell the client not to authenticate the server certificate, specify neither --ssl-ca nor --ssl-capath. The server still verifies the client according to any applicable requirements established for the client account, and it still uses any --ssl-ca or --ssl-capath option values specified at server startup.

• --ssl-capath=dir_name

The path to a directory that contains trusted SSL certificate authority certificates in PEM format. This option implies --ssl.

If you use encryption when establishing a client connection, to tell the client not to authenticate the server certificate, specify neither --ssl-ca nor --ssl-capath. The server still verifies the client according to any applicable requirements established for the client account, and it still uses any --ssl-ca or --ssl-capath option values specified at server startup.

MySQL distributions compiled using OpenSSL support the <code>--ssl-capath</code> option (see Section 5.9.1, "OpenSSL Versus yaSSL"). Distributions compiled using yaSSL do not because yaSSL does not look in any directory and does not follow a chained certificate tree. yaSSL requires that all components of the CA certificate tree be contained within a single CA certificate tree and that each certificate in the file has a unique SubjectName value. To work around this yaSSL limitation, concatenate the individual certificate files comprising the certificate tree into a new file and specify that file as the value of the <code>--ssl-ca</code> option.

• --ssl-cert=file name

The name of the SSL certificate file in PEM format to use for establishing a secure connection. This option implies --ss1.

• --ssl-cipher=cipher_list

A list of permissible ciphers to use for connection encryption. If no cipher in the list is supported, encrypted connections will not work. This option implies --ssl.

For greatest portability, <code>cipher_list</code> should be a list of one or more cipher names, separated by colons. This format is understood both by OpenSSL and yaSSL. Examples:

```
--ssl-cipher=AES128-SHA
--ssl-cipher=DHE-RSA-AES256-SHA:AES128-SHA
```

OpenSSL supports a more flexible syntax for specifying ciphers, as described in the OpenSSL documentation at http://www.openssl.org/docs/apps/ciphers.html. yaSSL does not, so attempts to use that extended syntax fail for a MySQL distribution compiled using yaSSL.

For information about which encryption ciphers MySQL supports, see Section 5.9.3, "Secure Connection Protocols and Ciphers".

• --ssl-crl=file_name

The path to a file containing certificate revocation lists in PEM format. This option implies --ssl.

If neither --ssl-crl nor --ssl-crlpath is given, no CRL checks are performed, even if the CA path contains certificate revocation lists.

MySQL distributions compiled using OpenSSL support the --ssl-crl option (see Section 5.9.1, "OpenSSL Versus yaSSL"). Distributions compiled using yaSSL do not because revocation lists do not work with yaSSL.

This option was added in MySQL 5.6.3.

• --ssl-crlpath=dir_name

The path to a directory that contains files containing certificate revocation lists in PEM format. This option implies --ss1.

If neither --ssl-crl nor --ssl-crlpath is given, no CRL checks are performed, even if the CA path contains certificate revocation lists.

MySQL distributions compiled using OpenSSL support the --ssl-crlpath option (see Section 5.9.1, "OpenSSL Versus yaSSL"). Distributions compiled using yaSSL do not because revocation lists do not work with yaSSL.

This option was added in MySQL 5.6.3.

• --ssl-key=file_name

The name of the SSL key file in PEM format to use for establishing a secure connection. This option implies --ssl.

If the MySQL distribution was built using OpenSSL or (as of MySQL 5.6.3) yaSSL and the key file is protected by a passphrase, the program prompts the user for the passphrase. The password must be given interactively; it cannot be stored in a file. If the passphrase is incorrect, the program continues as if it could not read the key. Before MySQL 5.6.3, if the MySQL distribution was built using yaSSL and the key file is protected by a passphrase, an error occurs.

• --ssl-mode=mode

This option is available only for client programs, not the server. It specifies the security state of the connection to the server. The following option values are permitted:

- DISABLED: Establish an unencrypted connection. This is like the legacy --ssl=0 option or its synonyms (--skip-ssl, --disable-ssl). This is the default if --ssl-mode is not specified.
- REQUIRED: Establish a secure connection if the server supports secure connections. The connection attempt fails if a secure connection cannot be established.

The --ssl-mode option was added in MySQL 5.6.30.

• --ssl-verify-server-cert

This option is available only for client programs, not the server. It causes the client to check the server's Common Name value in the certificate that the server sends to the client. The client verifies that name against the host name the client uses for connecting to the server, and the connection fails if there is a mismatch. For encrypted connections, this option helps prevent man-in-the-middle attacks. Verification is disabled by default.

5.10 Creating SSL and RSA Certificates and Keys

The following discussion describes how to create the files required for SSL and RSA support in MySQL. File creation is done by invoking the openssl command.

SSL certificate and key files enable MySQL to support secure connections using SSL. See Section 5.9, "Using Secure Connections".

RSA key files enable MySQL to support secure password exchange over unencrypted connections for accounts authenticated by the sha256_password plugin. See Section 6.1.4, "The SHA-256 Authentication Plugin".

5.10.1 Creating SSL Certificates and Keys Using openssl

This section describes how to use the <code>openssl</code> command to set up SSL certificate and key files for use by MySQL servers and clients. The first example shows a simplified procedure such as you might use from the command line. The second shows a script that contains more detail. The first two examples are intended for use on Unix and both use the <code>openssl</code> command that is part of OpenSSL. The third example describes how to set up SSL files on Windows.

Important

Whatever method you use to generate the certificate and key files, the Common Name value used for the server and client certificates/keys must each differ from the Common Name value used for the CA certificate. Otherwise, the certificate and key files will not work for servers compiled using OpenSSL. A typical error in this case is:

```
ERROR 2026 (HY000): SSL connection error:
error:00000001:lib(0):func(0):reason(1)
```

Example 1: Creating SSL Files from the Command Line on Unix

The following example shows a set of commands to create MySQL server and client certificate and key files. You will need to respond to several prompts by the openssl commands. To generate test files, you can press Enter to all prompts. To generate files for production use, you should provide nonempty responses.

```
# Create clean environment
shell> rm -rf newcerts
shell> mkdir newcerts && cd newcerts
# Create CA certificate
shell> openss1 genrsa 2048 > ca-key.pem
shell> openssl req -new -x509 -nodes -days 3600 \
        -key ca-key.pem -out ca.pem
# Create server certificate, remove passphrase, and sign it
# server-cert.pem = public key, server-key.pem = private key
shell> openss1 req -newkey rsa:2048 -days 3600 \
        -nodes -keyout server-key.pem -out server-req.pem
shell> openssl rsa -in server-key.pem -out server-key.pem
shell> openss1 x509 -req -in server-req.pem -days 3600 \
        -CA ca.pem -CAkey ca-key.pem -set_serial 01 -out server-cert.pem
# Create client certificate, remove passphrase, and sign it
# client-cert.pem = public key, client-key.pem = private key
shell> openss1 req -newkey rsa:2048 -days 3600 \
        -nodes -keyout client-key.pem -out client-req.pem
shell> openssl rsa -in client-key.pem -out client-key.pem
shell> openss1 x509 -req -in client-req.pem -days 3600 \
         -CA ca.pem -CAkey ca-key.pem -set_serial 01 -out client-cert.pem
```

After generating the certificates, verify them:

```
shell> openssl verify -CAfile ca.pem server-cert.pem client-cert.pem server-cert.pem: OK
```

```
client-cert.pem: OK
```

Now you have a set of files that can be used as follows:

- ca.pem: Use this as the argument to --ssl-ca on the server and client sides. (The CA certificate, if used, must be the same on both sides.)
- server-cert.pem, server-key.pem: Use these as the arguments to --ssl-cert and --ssl-key
 on the server side.
- client-cert.pem, client-key.pem: Use these as the arguments to --ssl-cert and --ssl-key
 on the client side.

To use the files for SSL connections, see Section 5.9.4, "Configuring MySQL to Use Secure Connections".

Example 2: Creating SSL Files Using a Script on Unix

Here is an example script that shows how to set up SSL certificate and key files for MySQL. After executing the script, use the files for SSL connections as described in Section 5.9.4, "Configuring MySQL to Use Secure Connections".

```
DIR=`pwd`/openssl
PRIV=$DIR/private
mkdir $DIR $PRIV $DIR/newcerts
cp /usr/share/ssl/openssl.cnf $DIR
replace ./demoCA $DIR -- $DIR/openssl.cnf
# Create necessary files: $database, $serial and $new_certs_dir
# directory (optional)
touch $DIR/index.txt
echo "01" > $DIR/serial
# Generation of Certificate Authority(CA)
openssl req -new -x509 -keyout $PRIV/cakey.pem -out $DIR/ca.pem \
   -days 3600 -config $DIR/openssl.cnf
# Sample output:
# Using configuration from /home/finley/openssl/openssl.cnf
# Generating a 1024 bit RSA private key
# writing new private key to '/home/finley/openssl/private/cakey.pem'
# Enter PEM pass phrase:
# Verifying password - Enter PEM pass phrase:
# You are about to be asked to enter information that will be
# incorporated into your certificate request.
# What you are about to enter is what is called a Distinguished Name
# There are quite a few fields but you can leave some blank
# For some fields there will be a default value,
# If you enter '.', the field will be left blank.
# Country Name (2 letter code) [AU]:FI
# State or Province Name (full name) [Some-State]:.
# Locality Name (eg, city) []:
# Organization Name (eg, company) [Internet Widgits Pty Ltd]:MySQL AB
# Organizational Unit Name (eg, section) []:
Common Name (eg, YOUR name) []:MySQL admin
# Email Address []:
# Create server request and key
openssl req -new -keyout $DIR/server-key.pem -out \
    $DIR/server-req.pem -days 3600 -config $DIR/openssl.cnf
```

```
# Sample output:
# Using configuration from /home/finley/openssl/openssl.cnf
# Generating a 1024 bit RSA private key
# writing new private key to '/home/finley/openssl/server-key.pem'
# Enter PEM pass phrase:
# Verifying password - Enter PEM pass phrase:
# You are about to be asked to enter information that will be
# incorporated into your certificate request.
# What you are about to enter is what is called a Distinguished Name
# or a DN.
# There are quite a few fields but you can leave some blank
# For some fields there will be a default value,
# If you enter '.', the field will be left blank.
# Country Name (2 letter code) [AU]:FI
# State or Province Name (full name) [Some-State]:.
# Locality Name (eg, city) []:
# Organization Name (eg, company) [Internet Widgits Pty Ltd]:MySQL AB
# Organizational Unit Name (eg, section) []:
# Common Name (eg, YOUR name) []:MySQL server
# Email Address []:
# Please enter the following 'extra' attributes
# to be sent with your certificate request
# A challenge password []:
# An optional company name []:
# Remove the passphrase from the key
openssl rsa -in $DIR/server-key.pem -out $DIR/server-key.pem
# Sign server cert
openssl ca -cert $DIR/ca.pem -policy policy_anything \
   -out $DIR/server-cert.pem -config $DIR/openssl.cnf \
   -infiles $DIR/server-req.pem
# Sample output:
# Using configuration from /home/finley/openssl/openssl.cnf
# Enter PEM pass phrase:
# Check that the request matches the signature
# Signature ok
# The Subjects Distinguished Name is as follows
# countryName :PRINTABLE:'FI'
# organizationName
                       :PRINTABLE: 'MySQL AB'
                       :PRINTABLE: 'MySQL admin'
# Certificate is to be certified until Sep 13 14:22:46 2003 GMT
# (365 days)
\# Sign the certificate? [y/n]:y
# 1 out of 1 certificate requests certified, commit? [y/n]y
# Write out database with 1 new entries
# Data Base Updated
# Create client request and key
openssl req -new -keyout $DIR/client-key.pem -out \
   $DIR/client-req.pem -days 3600 -config $DIR/openssl.cnf
# Sample output:
# Using configuration from /home/finley/openssl/openssl.cnf
# Generating a 1024 bit RSA private key
# .......++++++
# writing new private key to '/home/finley/openssl/client-key.pem'
```

```
# Enter PEM pass phrase:
# Verifying password - Enter PEM pass phrase:
# You are about to be asked to enter information that will be
# incorporated into your certificate request.
# What you are about to enter is what is called a Distinguished Name
# or a DN.
# There are quite a few fields but you can leave some blank
# For some fields there will be a default value,
# If you enter '.', the field will be left blank.
# Country Name (2 letter code) [AU]:FI
# State or Province Name (full name) [Some-State]:.
# Locality Name (eg, city) []:
# Organization Name (eg, company) [Internet Widgits Pty Ltd]:MySQL AB
# Organizational Unit Name (eg, section) []:
# Common Name (eg, YOUR name) []:MySQL user
# Email Address []:
# Please enter the following 'extra' attributes
# to be sent with your certificate request
# A challenge password []:
# An optional company name []:
# Remove the passphrase from the key
openssl rsa -in $DIR/client-key.pem -out $DIR/client-key.pem
# Sign client cert
openssl ca -cert $DIR/ca.pem -policy policy_anything \
    -out $DIR/client-cert.pem -config $DIR/openssl.cnf \
    -infiles $DIR/client-req.pem
# Sample output:
# Using configuration from /home/finley/openssl/openssl.cnf
# Enter PEM pass phrase:
# Check that the request matches the signature
# Signature ok
# The Subjects Distinguished Name is as follows
# countryName
                      :PRINTABLE:'FI'
# organizationName
                        :PRINTABLE: 'MySQL AB'
                        :PRINTABLE: 'MySQL user'
# commonName
# Certificate is to be certified until Sep 13 16:45:17 2003 GMT
# (365 days)
# Sign the certificate? [y/n]:y
\# 1 out of 1 certificate requests certified, commit? [y/n]y
# Write out database with 1 new entries
# Data Base Updated
# Create a my.cnf file that you can use to test the certificates
cat <<EOF > $DIR/my.cnf
[client]
ssl-ca=$DIR/ca.pem
ssl-cert=$DIR/client-cert.pem
ssl-key=$DIR/client-key.pem
[mysqld]
ssl-ca=$DIR/ca.pem
ssl-cert=$DIR/server-cert.pem
ssl-key=$DIR/server-key.pem
EOF
```

Example 3: Creating SSL Files on Windows

Download OpenSSL for Windows if it is not installed on your system. An overview of available packages can be seen here:

```
http://www.slproweb.com/products/Win32OpenSSL.html
```

Choose the Win32 OpenSSL Light or Win64 OpenSSL Light package, depending on your architecture (32-bit or 64-bit). The default installation location will be C:\OpenSSL-Win32 or C:\OpenSSL-Win64, depending on which package you downloaded. The following instructions assume a default location of C:\OpenSSL-Win32. Modify this as necessary if you are using the 64-bit package.

If a message occurs during setup indicating '...critical component is missing: Microsoft Visual C++ 2008 Redistributables', cancel the setup and download one of the following packages as well, again depending on your architecture (32-bit or 64-bit):

• Visual C++ 2008 Redistributables (x86), available at:

```
http://www.microsoft.com/downloads/details.aspx?familyid=9B2DA534-3E03-4391-8A4D-074B9F2BC1BF
```

Visual C++ 2008 Redistributables (x64), available at:

```
http://www.microsoft.com/downloads/details.aspx?familyid=bd2a6171-e2d6-4230-b809-9a8d7548clb6
```

After installing the additional package, restart the OpenSSL setup procedure.

During installation, leave the default C:\OpenSSL-Win32 as the install path, and also leave the default option 'Copy OpenSSL DLL files to the Windows system directory' selected.

When the installation has finished, add C:\OpenSSL-Win32\bin to the Windows System Path variable of your server:

- 1. On the Windows desktop, right-click the **My Computer** icon, and select **Properties**.
- 2. Select the **Advanced** tab from the **System Properties** menu that appears, and click the **Environment Variables** button.
- 3. Under **System Variables**, select **Path**, then click the **Edit** button. The **Edit System Variable** dialogue should appear.
- 4. Add ';C:\OpenSSL-Win32\bin' to the end (notice the semicolon).
- 5. Press OK 3 times.
- 6. Check that OpenSSL was correctly integrated into the Path variable by opening a new command console (Start>Run>cmd.exe) and verifying that OpenSSL is available:

```
Microsoft Windows [Version ...]

Copyright (c) 2006 Microsoft Corporation. All rights reserved.

C:\Windows\system32>cd \

C:\>openssl

OpenSSL> exit <<< If you see the OpenSSL prompt, installation was successful.

C:\>
```

Depending on your version of Windows, the preceding path-setting instructions might differ slightly.

After OpenSSL has been installed, use instructions similar to those from Example 1 (shown earlier in this section), with the following changes:

Change the following Unix commands:

```
# Create clean environment
shell> rm -rf newcerts
shell> mkdir newcerts && cd newcerts
```

On Windows, use these commands instead:

```
# Create clean environment
C:\> md c:\newcerts
C:\> cd c:\newcerts
```

• When a '\' character is shown at the end of a command line, this '\' character must be removed and the command lines entered all on a single line.

After generating the certificate and key files, to use them for SSL connections, see Section 5.9.4, "Configuring MySQL to Use Secure Connections".

5.10.2 Creating RSA Keys Using openssl

This section describes how to use the openss1 command to set up the RSA key files that enable MySQL to support secure password exchange over unencrypted connections for accounts authenticated by the sha256_password plugin.

To create the RSA private and public key-pair files, run these commands while logged into the system account used to run the MySQL server so the files will be owned by that account:

```
openssl genrsa -out private_key.pem 2048
openssl rsa -in private_key.pem -pubout -out public_key.pem
```

Those commands create 2,048-bit keys. To create stronger keys, use a larger value.

Then set the access modes for the key files. The private key should be readable only by the server, whereas the public key can be freely distributed to client users:

```
chmod 400 private_key.pem
chmod 444 public_key.pem
```

5.11 Connecting to MySQL Remotely from Windows with SSH

This section describes how to get a secure connection to a remote MySQL server with SSH. The original information was provided by David Carlson compleomm.com.

- 1. Install an SSH client on your Windows machine. For a comparison of SSH clients, see http://en.wikipedia.org/wiki/Comparison_of_SSH_clients.
- 2. Start your Windows SSH client. Set Host_Name = yourmysqlserver_URL_or_IP. Set userid=your_userid to log in to your server. This userid value might not be the same as the user name of your MySQL account.
- 3. Set up port forwarding. Either do a remote forward (Set local_port: 3306, remote_host: yourmysqlservername_or_ip, remote_port: 3306) or a local forward (Set port: 3306, host: localhost, remote port: 3306).

- 4. Save everything, otherwise you will have to redo it the next time.
- 5. Log in to your server with the SSH session you just created.
- 6. On your Windows machine, start some ODBC application (such as Access).
- 7. Create a new file in Windows and link to MySQL using the ODBC driver the same way you normally do, except type in localhost for the MySQL host server, not yourmysqlservername.

At this point, you should have an ODBC connection to MySQL, encrypted using SSH.

5.12 SQL-Based MySQL Account Activity Auditing

Applications can use the following guidelines to perform SQL-based auditing that ties database activity to MySQL accounts.

MySQL accounts correspond to rows in the <code>mysql.user</code> table. When a client connects successfully, the server authenticates the client to a particular row in this table. The <code>User</code> and <code>Host</code> column values in this row uniquely identify the account and correspond to the <code>'user_name'@'host_name'</code> format in which account names are written in SQL statements.

The account used to authenticate a client determines which privileges the client has. Normally, the CURRENT_USER() function can be invoked to determine which account this is for the client user. Its value is constructed from the User and Host columns of the user table row for the account.

However, there are circumstances under which the CURRENT_USER() value corresponds not to the client user but to a different account. This occurs in contexts when privilege checking is not based the client's account:

- Stored routines (procedures and functions) defined with the SQL SECURITY DEFINER characteristic
- Views defined with the SQL SECURITY DEFINER characteristic
- · Triggers and events

In those contexts, privilege checking is done against the DEFINER account and CURRENT_USER() refers to that account, not to the account for the client who invoked the stored routine or view or who caused the trigger to activate. To determine the invoking user, you can call the USER() function, which returns a value indicating the actual user name provided by the client and the host from which the client connected. However, this value does not necessarily correspond directly to an account in the user table, because the USER() value never contains wildcards, whereas account values (as returned by CURRENT_USER()) may contain user name and host name wildcards.

For example, a blank user name matches any user, so an account of ''@'localhost' enables clients to connect as an anonymous user from the local host with any user name. In this case, if a client connects as user1 from the local host, USER() and CURRENT_USER() return different values:

The host name part of an account can contain wildcards, too. If the host name contains a '%' or '_' pattern character or uses netmask notation, the account can be used for clients connecting from multiple hosts and the CURRENT_USER() value will not indicate which one. For example, the account

'user2'@'%.example.com' can be used by user2 to connect from any host in the example.com domain. If user2 connects from remote.example.com, USER() and CURRENT_USER() return different values:

If an application must invoke USER() for user auditing (for example, if it does auditing from within triggers) but must also be able to associate the USER() value with an account in the user table, it is necessary to avoid accounts that contain wildcards in the User or Host column. Specifically, do not permit User to be empty (which creates an anonymous-user account), and do not permit pattern characters or netmask notation in Host values. All accounts must have a nonempty User value and literal Host value.

With respect to the previous examples, the ''@'localhost' and 'user2'@'%.example.com' accounts should be changed not to use wildcards:

```
RENAME USER ''@'localhost' TO 'userl'@'localhost';
RENAME USER 'user2'@'%.example.com' TO 'user2'@'remote.example.com';
```

If user2 must be able to connect from several hosts in the example.com domain, there should be a separate account for each host.

To extract the user name or host name part from a CURRENT_USER() or USER() value, use the SUBSTRING_INDEX() function:

Chapter 6 Security Plugins

Table of Contents

6.1 Authentication Plugins	96
6.1.1 The Native Authentication Plugin	96
6.1.2 The Old Native Authentication Plugin	96
6.1.3 Migrating Away from Pre-4.1 Password Hashing and the mysql_old_password Plugin	97
6.1.4 The SHA-256 Authentication Plugin	101
6.1.5 The PAM Authentication Plugin	104
6.1.6 The Windows Native Authentication Plugin	112
6.1.7 The Cleartext Client-Side Authentication Plugin	117
6.1.8 The Socket Peer-Credential Authentication Plugin	118
6.1.9 The Test Authentication Plugin	118
6.2 The Password Validation Plugin	119
6.2.1 Password Validation Plugin Installation	120
6.2.2 Password Validation Plugin Options and Variables	120
6.3 MySQL Enterprise Audit	125
6.3.1 Installing MySQL Enterprise Audit	127
6.3.2 MySQL Enterprise Audit Security Considerations	128
6.3.3 The Audit Log File	128
6.3.4 Audit Log Logging Control	138
6.3.5 Audit Log Filtering	140
6.3.6 Audit Log Reference	
6.3.7 Audit Log Restrictions	
6.4 MySQL Enterprise Firewall	151
6.4.1 MySQL Enterprise Firewall Components	
6.4.2 Installing or Uninstalling MySQL Enterprise Firewall	
6.4.3 Using MySQL Enterprise Firewall	
6.4.4 MySQL Enterprise Firewall Reference	159

MySQL includes several plugins that implement security features:

- Plugins for authenticating attempts by clients to connect to MySQL Server. Plugins are available for several authentication protocols. For general discussion of the authentication process, see Section 5.7, "Pluggable Authentication". For characteristics of specific authentication plugins, see Section 6.1, "Authentication Plugins".
- A password-validation plugin for implementing password strength policies and assessing the strength of potential passwords. See Section 6.2, "The Password Validation Plugin".
- (MySQL Enterprise Edition only) MySQL Enterprise Audit, implemented using a server plugin, uses the
 open MySQL Audit API to enable standard, policy-based monitoring and logging of connection and query
 activity executed on specific MySQL servers. Designed to meet the Oracle audit specification, MySQL
 Enterprise Audit provides an out of box, easy to use auditing and compliance solution for applications
 that are governed by both internal and external regulatory guidelines.
- (MySQL Enterprise Edition only) MySQL Enterprise Firewall, an application-level firewall that enables
 database administrators to permit or deny SQL statement execution based on matching against
 whitelists of accepted statement patterns. This helps harden MySQL Server against attacks such as
 SQL injection or attempts to exploit applications by using them outside of their legitimate query workload
 characteristics.

6.1 Authentication Plugins

The following sections describe the authentication plugins available in MySQL.

The default plugin is mysql_native_password unless the --default-authentication-plugin option is set otherwise at server startup.

6.1.1 The Native Authentication Plugin

MySQL includes two plugins that implement native authentication; that is, authentication against passwords stored in the Password column of the mysql.user table. This section describes mysql_native_password, which implements authentication against the mysql.user table using the native password hashing method. For information about mysql_old_password, which implements authentication using the older (pre-4.1) password hashing method, see Section 6.1.2, "The Old Native Authentication Plugin". For information about these password hashing methods, see Section 2.2.4, "Password Hashing in MySQL".

The mysql_native_password native authentication plugin is backward compatible. Clients older than MySQL 5.5.7 do not support authentication *plugins* but do use the native authentication *protocol*, so they can connect to servers from MySQL 5.5.7 and up.

The following table shows the plugin names on the server and client sides.

Table 6.1 MySQL Native Password Authentication Plugin

Server-side plugin name	mysql_native_password
Client-side plugin name	mysql_native_password
Library file name	None (plugins are built in)

The plugin exists in both client and server form:

- The server-side plugin is built into the server, need not be loaded explicitly, and cannot be disabled by unloading it.
- The client-side plugin is built into the libmysqlclient client library as of MySQL 5.5.7 and available to any program linked against libmysqlclient from that version or higher.
- MySQL client programs use mysql_native_password by default. The --default-auth option can be used as a hint about which client-side plugin the program can expect to use:

```
shell> mysql --default-auth=mysql_native_password ...
```

If an account row specifies no plugin name, the server authenticates the account using either the <code>mysql_native_password</code> or <code>mysql_old_password</code> plugin, depending on whether the password hash value in the <code>Password</code> column used native hashing or the older pre-4.1 hashing method. Clients must match the password in the <code>Password</code> column of the account row.

For general information about pluggable authentication in MySQL, see Section 5.7, "Pluggable Authentication".

6.1.2 The Old Native Authentication Plugin

MySQL includes two plugins that implement native authentication; that is, authentication against passwords stored in the Password column of the mysql.user table. This section describes mysql_old_password, which implements authentication against the mysql.user table using the older (pre-4.1) password hashing method. For information about mysql native password, which implements

authentication using the native password hashing method, see Section 6.1.1, "The Native Authentication Plugin". For information about these password hashing methods, see Section 2.2.4, "Password Hashing in MySQL".

Note

Passwords that use the pre-4.1 hashing method are less secure than passwords that use the native password hashing method and should be avoided. Pre-4.1 passwords are deprecated and support for them will be removed in a future MySQL release. For account upgrade instructions, see Section 6.1.3, "Migrating Away from Pre-4.1 Password Hashing and the mysql old password Plugin".

The mysql_old_password native authentication plugin is backward compatible. Clients older than MySQL 5.5.7 do not support authentication *plugins* but do use the native authentication *protocol*, so they can connect to servers from MySQL 5.5.7 and up.

The following table shows the plugin names on the server and client sides.

Table 6.2 MySQL Old Native Authentication Plugin

Server-side plugin name	mysql_old_password
Client-side plugin name	mysql_old_password
Library file name	None (plugins are built in)

The plugin exists in both client and server form:

- The server-side plugin is built into the server, need not be loaded explicitly, and cannot be disabled by unloading it.
- The client-side plugin is built into the libmysqlclient client library as of MySQL 5.5.7 and available to any program linked against libmysqlclient from that version or higher.
- MySQL client programs can use the --default-auth option to specify the mysql_old_password plugin as a hint about which client-side plugin the program can expect to use:

```
shell> mysql --default-auth=mysql_old_password ...
```

If an account row specifies no plugin name, the server authenticates the account using either the <code>mysql_native_password</code> or <code>mysql_old_password</code> plugin, depending on whether the password hash value in the <code>Password</code> column used native hashing or the older pre-4.1 hashing method. Clients must match the password in the <code>Password</code> column of the account row.

For general information about pluggable authentication in MySQL, see Section 5.7, "Pluggable Authentication".

6.1.3 Migrating Away from Pre-4.1 Password Hashing and the mysql_old_password Plugin

The MySQL server authenticates connection attempts for each account listed in the mysql.user table using the authentication plugin named in the plugin column. If the plugin column is empty, the server authenticates the account as follows:

• Before MySQL 5.7.2, the server uses the mysql_native_password or mysql_old_password plugin implicitly, depending on the format of the password hash in the Password column. If the Password value is empty or a 4.1 password hash (41 characters), the server uses mysql_native_password. If the password value is a pre-4.1 password hash (16 characters),

the server uses mysql_old_password. (For additional information about these hash formats, see Section 2.2.4, "Password Hashing in MySQL".)

• As of MySQL 5.7.2, the server requires the plugin column to be nonempty and disables accounts that have an empty plugin value.

Pre-4.1 password hashes and the mysql_old_password plugin are deprecated as of MySQL 5.6.5 and support for them is removed in MySQL 5.7.5. They provide a level of security inferior to that offered by 4.1 password hashing and the mysql_native_password plugin.

Given the requirement in MySQL 5.7.2 that the plugin column must be nonempty, coupled with removal of mysql_old_password support in 5.7.5, DBAs are advised to upgrade accounts as follows:

- Upgrade accounts that use mysql_native_password implicitly to use it explicitly
- Upgrade accounts that use mysql_old_password (either implicitly or explicitly) to use mysql_native_password explicitly

The instructions in this section describe how to perform those upgrades. The result is that no account has an empty plugin value and no account uses pre-4.1 password hashing or the mysql_old_password plugin.

As a variant on these instructions, DBAs might offer users the choice to upgrade to the sha256_password plugin, which authenticates using SHA-256 password hashes. For information about this plugin, see Section 6.1.4, "The SHA-256 Authentication Plugin".

The following table lists the types of mysql.user accounts considered in this discussion.

plugin Column	Password Column	Authentication Result	Upgrade Action
Empty	Empty	Implicitly uses mysql_native_password	Assign plugin
Empty	4.1 hash	Implicitly uses mysql_native_password	Assign plugin
Empty	Pre-4.1 hash	Implicitly uses mysql_old_password	Assign plugin, rehash password
mysql_native_password	Empty	Explicitly uses mysql_native_password	None
mysql_native_password	4.1 hash	Explicitly uses mysql_native_password	None
mysql_old_password	Empty	Explicitly uses mysql_old_password	Upgrade plugin
mysql_old_password	Pre-4.1 hash	Explicitly uses mysql_old_password	Upgrade plugin, rehash password

Accounts corresponding to lines for the mysql_native_password plugin require no upgrade action (because no change of plugin or hash format is required). For accounts corresponding to lines for which the password is empty, consider asking the account owners to choose a password (or require it by using ALTER USER to expire empty account passwords).

Upgrading Accounts from Implicit to Explicit mysql_native_password Use

Accounts that have an empty plugin and a 4.1 password hash use mysql_native_password implicitly. To upgrade these accounts to use mysql_native_password explicitly, execute these statements:

```
UPDATE mysql.user SET plugin = 'mysql_native_password'
WHERE plugin = '' AND (Password = '' OR LENGTH(Password) = 41);
FLUSH PRIVILEGES;
```

Before MySQL 5.7.2, you can execute those statements to uprade accounts proactively. As of MySQL 5.7.2, you can run mysql_upgrade, which performs the same operation among its upgrade actions.

Notes:

- The upgrade operation just described is safe to execute at any time because it makes the mysql_native_password plugin explicit only for accounts that already use it implicitly.
- This operation requires no password changes, so it can be performed without affecting users or requiring their involvement in the upgrade process.

Upgrading Accounts from mysql_old_password to mysql_native_password

Accounts that use mysql_old_password (either implicitly or explicitly) should be upgraded to use mysql_native_password explicitly. This requires changing the plugin *and* changing the password from pre-4.1 to 4.1 hash format.

For the accounts covered in this step that must be upgraded, one of these conditions is true:

- The account uses mysql_old_password implicitly because the plugin column is empty and the password has the pre-4.1 hash format (16 characters).
- The account uses mysql_old_password explicitly.

To identify such accounts, use this query:

```
SELECT User, Host, Password FROM mysql.user
WHERE (plugin = '' AND LENGTH(Password) = 16)
OR plugin = 'mysql_old_password';
```

The following discussion provides two methods for updating that set of accounts. They have differing characteristics, so read both and decide which is most suitable for a given MySQL installation.

Method 1.

Characteristics of this method:

- It requires that server and clients be run with secure_auth=0 until all users have been upgraded to mysql_native_password. (Otherwise, users cannot connect to the server using their old-format password hashes for the purpose of upgrading to a new-format hash.)
- It works for MySQL 5.5 through 5.7.1. As of 5.7.2, it does not work because the server requires accounts to have a nonempty plugin and disables them otherwise. Therefore, if you have already upgraded to 5.7.2 or later, choose Method 2, described later.

You should ensure that the server is running with secure_auth=0.

For all accounts that use mysql_old_password explicitly, set them to the empty plugin:

```
UPDATE mysql.user SET plugin = ''
WHERE plugin = 'mysql_old_password';
FLUSH PRIVILEGES;
```

To also expire the password for affected accounts, use these statements instead:

```
UPDATE mysql.user SET plugin = '', password_expired = 'Y'
```

```
WHERE plugin = 'mysql_old_password';
FLUSH PRIVILEGES;
```

Now affected users can reset their password to use 4.1 hashing. Ask each user who now has an empty plugin to connect to the server and execute these statements:

```
SET old_passwords = 0;
SET PASSWORD = PASSWORD('user-chosen-password');
```

Note

In MySQL 5.6.5 or later, the client-side --secure-auth option is enabled by default, so remind users to disable it or they will be unable to connect:

```
shell> mysql -u user_name -p --secure-auth=0
```

After an affected user has executed those statements, you can set the corresponding account plugin to mysql_native_password to make the plugin explicit. Or you can periodically run these statements to find and fix any accounts for which affected users have reset their password:

```
UPDATE mysql.user SET plugin = 'mysql_native_password'
WHERE plugin = '' AND (Password = '' OR LENGTH(Password) = 41);
FLUSH PRIVILEGES;
```

When there are no more accounts with an empty plugin, this query returns an empty result:

```
SELECT User, Host, Password FROM mysql.user
WHERE (plugin = '' AND LENGTH(Password) = 16);
```

At that point, all accounts have been migrated away from pre-4.1 password hashing and the server no longer need be run with secure_auth=0.

Method 2.

Characteristics of this method:

- It assigns each affected account a new password, so you must tell each such user the new password
 and ask the user to choose a new one. Communication of passwords to users is outside the scope of
 MySQL, but should be done carefully.
- It does not require server or clients to be run with secure_auth=0.
- It works for any version of MySQL 5.5 or later (and for 5.7.6 or later has an easier variant).

With this method, you update each account separately due to the need to set passwords individually. Choose a different password for each account.

Suppose that 'user1'@'localhost' is one of the accounts to be upgraded. Modify it as follows:

• In MySQL 5.7.6 and higher, ALTER USER provides the capability of modifying both the account password and its authentication plugin, so you need not modify the mysql.user table directly:

```
ALTER USER 'userl'@'localhost'
IDENTIFIED WITH mysql_native_password BY 'DBA-chosen-password';
```

To also expire the account password, use this statement instead:

```
ALTER USER 'userl'@'localhost'
IDENTIFIED WITH mysql_native_password BY 'DBA-chosen-password'
PASSWORD EXPIRE;
```

Then tell the user the new password and ask the user to connect to the server with that password and execute this statement to choose a new password:

```
ALTER USER () IDENTIFIED BY 'user-chosen-password';
```

Before MySQL 5.7.6, you must modify the mysql.user table directly using these statements:

```
SET old_passwords = 0;
UPDATE mysql.user SET plugin = 'mysql_native_password',
Password = PASSWORD('DBA-chosen-password')
WHERE (User, Host) = ('userl', 'localhost');
FLUSH PRIVILEGES;
```

To also expire the account password, use these statements instead:

```
SET old_passwords = 0;
UPDATE mysql.user SET plugin = 'mysql_native_password',
Password = PASSWORD('DBA-chosen-password'), password_expired = 'Y'
WHERE (User, Host) = ('userl', 'localhost');
FLUSH PRIVILEGES;
```

Then tell the user the new password and ask the user to connect to the server with that password and execute these statements to choose a new password:

```
SET old_passwords = 0;
SET PASSWORD = PASSWORD('user-chosen-password');
```

Repeat for each account to be upgraded.

6.1.4 The SHA-256 Authentication Plugin

As of MySQL 5.6.6, MySQL provides an authentication plugin that implements SHA-256 hashing for user account passwords.

Important

To connect to the server using an account that authenticates with the sha256_password plugin, you must use either an SSL connection or an unencrypted connection that encrypts the password using RSA, as described later in this section. Either way, use of the sha256_password plugin requires that MySQL be built with SSL capabilities. See Section 5.9, "Using Secure Connections".

The following table shows the plugin names on the server and client sides.

Table 6.3 MySQL SHA-256 Authentication Plugin

Server-side plugin name	sha256_password
Client-side plugin name	sha256_password
Library file name	None (plugins are built in)

The server-side sha256_password plugin is built into the server, need not be loaded explicitly, and cannot be disabled by unloading it. Similarly, clients need not specify the location of the client-side plugin.

To set up an account that uses SHA-256 password hashing, use the following procedure.

1. Create the account and specify that it authenticates using the sha256 password plugin:

```
CREATE USER 'sha256user'@'localhost' IDENTIFIED WITH sha256_password;
```

2. Set the old_passwords system variable to 2 to cause the PASSWORD() function to use SHA-256 hashing of password strings, then set the account password:

```
SET old_passwords = 2;
SET PASSWORD FOR 'sha256user'@'localhost' = PASSWORD('Sh@256Pa33');
```

Alternatively, start the server with the default authentication plugin set to sha256_password. For example, put these lines in the server option file:

```
[mysqld]
default-authentication-plugin=sha256_password
```

That causes the sha256_password plugin to be used by default for new accounts. As a result, it is possible to create the account and set its password without naming the plugin explicitly using this CREATE USER syntax:

```
CREATE USER 'sha256user'@'localhost' IDENTIFIED BY 'Sh@256Pa33';
```

In this case, the server assigns the sha256_password plugin to the account and encrypts the password using SHA-256.

Accounts in the <code>mysql.user</code> table that use SHA-256 passwords can be identified as rows with <code>'sha256_password'</code> in the <code>plugin</code> column and a SHA-256 password hash in the <code>authentication_string</code> column.

Another consequence of using sha256_password as the default authentication plugin is that to create an account that uses a different plugin, you must specify that plugin using an IDENTIFIED WITH clause in the CREATE USER statement, then set old_passwords appropriately for the plugin before using SET PASSWORD to set the account password. For example, to use the mysql_native_password plugin, do this:

```
CREATE USER 'nativeuser'@'localhost' IDENTIFIED WITH mysql_native_password;
SET old_passwords = 0;
SET PASSWORD FOR 'nativeuser'@'localhost' = PASSWORD('N@tivePa33');
```

To set or change the password for any account that authenticates using the sha256_password plugin, be sure that the value of old_passwords is 2 before using SET_PASSWORD. If old_passwords has a value other than 2, an error occurs for attempts to set the password:

```
mysql> SET old_passwords = 0;
mysql> SET PASSWORD FOR 'sha256user'@'localhost' = PASSWORD('NewSh@256Pa33');
ERROR 1827 (HY000): The password hash doesn't have the expected format.
Check if the correct password algorithm is being used with the
PASSWORD() function.
```

For more information about old_passwords and PASSWORD(), see Server System Variables, and Encryption and Compression Functions.

MySQL can be compiled using either OpenSSL or yaSSL (see Section 5.9.1, "OpenSSL Versus yaSSL"). The sha256_password plugin works with distributions compiled using either package, but if MySQL is

compiled using OpenSSL, RSA encryption is available and sha256_password implements the following additional capabilities. (To enable these capabilities, you must also follow the RSA configuration procedure given later in this section.)

- It is possible for the client to transmit passwords to the server using RSA encryption during the client connection process, as described later.
- The server exposes two additional system variables, sha256_password_private_key_path and sha256_password_public_key_path. It is intended that the database administrator will set these to the names of the RSA private and public key-pair files at server startup if the key files have names that differ from the system variable default values.
- The server exposes a status variable, Rsa_public_key, that displays the RSA public key value.
- The mysql and mysqltest client programs support a --server-public-key-path option for specifying an RSA public key file explicitly. (This option was added in MySQL 5.6.6 under the name --server-public-key and renamed in 5.6.7 to --server-public-key-path.)

For clients that use the sha256_password plugin, passwords are never exposed as cleartext when connecting to the server. How password transmission occurs depends on whether an SSL connection is used and whether RSA encryption is available:

- If an SSL connection is used, the password is sent as cleartext but cannot be snooped because the connection is encrypted using SSL.
- If an SSL connection is not used but RSA encryption is available, the password is sent within an unencrypted connection, but the password is RSA-encrypted to prevent snooping. When the server receives the password, it decrypts it. A scramble is used in the encryption to prevent repeat attacks.
- If an SSL connection is not used and RSA encryption is not available, the sha256_password plugin causes the connection attempt to fail because the password cannot be sent without being exposed as cleartext.

As mentioned previously, RSA password encryption is available only if MySQL was compiled using OpenSSL. The implication for MySQL distributions compiled using yaSSL is that SHA-256 passwords can be used only when clients use SSL to access the server. See Section 5.9.4, "Configuring MySQL to Use Secure Connections".

Assuming that MySQL has been compiled using OpenSSL, the following procedure describes how to enable RSA encryption of passwords during the client connection process:

- Create the RSA private and public key-pair files using the instructions in Section 5.10, "Creating SSL and RSA Certificates and Keys".
- 2. If the private and public key files are located in the data directory and are named private_key.pem and public_key.pem (the default values of the sha256_password_private_key_path and sha256_password_public_key_path system variables), the server will use them automatically at startup.

Otherwise, in the server option file, set the system variables to the key file names. If the files are located in the server data directory, you need not specify their full path names:

```
[mysqld]
sha256_password_private_key_path=myprivkey.pem
sha256_password_public_key_path=mypubkey.pem
```

If the key files are not located in the data directory, or to make their locations explicit in the system variable values, use full path names:

```
[mysqld]
sha256_password_private_key_path=/usr/local/mysql/myprivkey.pem
sha256_password_public_key_path=/usr/local/mysql/mypubkey.pem
```

3. Restart the server, then connect to it and check the Rsa_public_key status variable value. The value will differ from that shown here, but should be nonempty:

If the value is empty, the server found some problem with the key files. Check the error log for diagnostic information.

After the server has been configured with the RSA key files, clients have the option of using them to connect to the server using accounts that authenticate with the sha256_password plugin. As mentioned previously, such accounts can use either an SSL connection (in which case RSA is not used) or an unencrypted connection that encrypts the password using RSA. Assume for the following discussion that SSL is not used. Connecting to the server involves no special preparation on the client side. For example:

```
shell> mysql --ssl=0 -u sha256user -p
Enter password: Sh@256Pa33
```

For connection attempts by sha256user, the server determines that sha256_password is the appropriate authentication plugin and invokes it. The plugin finds that the connection does not use SSL and thus requires the password to be transmitted using RSA encryption. In this case, the plugin sends the RSA public key to the client, which uses it to encrypt the password and returns the result to the server. The plugin uses the RSA key on the server side to decrypt the password and accepts or rejects the connection based on whether the password is correct.

The server sends the public key to the client as needed, but if a copy of the RSA public key is available on the client host, the client can use it to save a round trip in the client/server protocol:

```
shell> mysql --ssl=0 -u sha256user -p --server-public-key-path=file_name
```

The public key value in the file named by the <code>--server-public-key-path</code> option should be the same as the key value in the server-side file named by the <code>sha256_password_public_key_path</code> system variable. If the key file contains a valid public key value but the value is incorrect, an access-denied error occurs. If the key file does not contain a valid public key, the client program cannot use it. In this case, the <code>sha256_password</code> plugin sends the public key to the client as if no <code>--server-public-key-path</code> option had been specified.

Client users can get the RSA public key two ways:

- The database administrator can provide a copy of the public key file.
- A client user who can connect to the server some other way can use a SHOW STATUS LIKE 'Rsa_public_key' statement and save the returned key value in a file.

6.1.5 The PAM Authentication Plugin

Note

The PAM authentication plugin is an extension included in MySQL Enterprise Edition, a commercial product. To learn more about commercial products, see http://www.mysgl.com/products/.

As of MySQL 5.6.10, MySQL Enterprise Edition includes an authentication plugin that enables MySQL Server to use PAM (Pluggable Authentication Modules) to authenticate MySQL users. PAM enables a system to use a standard interface to access various kinds of authentication methods, such as Unix passwords or an LDAP directory.

The PAM authentication plugin provides these capabilities:

- External authentication: The plugin enables MySQL Server to accept connections from users defined outside the MySQL grant tables and that authenticate using methods supported by PAM.
- Proxy user support: The plugin can return to MySQL a user name different from the login user, based
 on the groups the external user is in and the authentication string provided. This means that the plugin
 can return the MySQL user that defines the privileges the external PAM-authenticated user should have.
 For example, a PAM user named joe can connect and have the privileges of the MySQL user named
 developer.

The PAM authentication plugin has been tested on Linux and Mac OS X.

The PAM plugin uses the information passed to it by MySQL Server (such as user name, host name, password, and authentication string), plus whatever method is available for PAM lookup. The plugin checks the user credentials against PAM and returns 'Authentication succeeded, Username is user_name' or 'Authentication failed'.

The following table shows the plugin and library file names. The file name suffix might be different on your system. The file location must be the directory named by the plugin_dir system variable. For installation information, see Section 6.1.5.1, "Installing the PAM Authentication Plugin".

Table 6.4 MySQL PAM Authentication Plugin

Server-side plugin name authentication_pam			
Client-side plugin name	mysql_clear_password		
Library file name	authentication_pam.so		

The library file includes only the server-side plugin. The client-side plugin is built into the libmysqlclient client library. See Section 6.1.7, "The Cleartext Client-Side Authentication Plugin".

The server-side PAM authentication plugin is included only in MySQL Enterprise Edition. It is not included in MySQL community distributions. The client-side clear-text plugin that communicates with the server-side plugin is built into the MySQL client library and is included in all distributions, including community distributions. This permits clients from any MySQL 5.6.10 or higher distribution to connect to a server that has the server-side plugin loaded.

For general information about pluggable authentication in MySQL, see Section 5.7, "Pluggable Authentication". For proxy user information, see Section 5.8, "Proxy Users".

6.1.5.1 Installing the PAM Authentication Plugin

The PAM authentication plugin must be located in the MySQL plugin directory (the directory named by the plugin_dir system variable). If necessary, set the value of plugin_dir at server startup to tell the server the location of the plugin directory.

To enable the plugin, start the server with the --plugin-load option. For example, put the following lines in your my.cnf file. If library files have a suffix different from .so on your system, substitute the correct suffix.

```
[mysqld]
plugin-load=authentication_pam.so
```

To verify plugin installation, examine the INFORMATION_SCHEMA.PLUGINS table or use the SHOW PLUGINS statement (see Obtaining Server Plugin Information). For example:

To associate a MySQL account with the PAM plugin, use the plugin name authentication_pam in the IDENTIFIED WITH clause of CREATE USER or GRANT statement that creates the account.

6.1.5.2 Using the PAM Authentication Plugin

This section describes how to use the PAM authentication plugin to connect from MySQL client programs to the server. It is assumed that the server-side plugin is enabled, as described previously.

Note

The client-side plugin with which the PAM plugin communicates simply sends the password to the server in clear text so it can be passed to PAM. This may be a security problem in some configurations, but is necessary to use the server-side PAM library. To avoid problems if there is any possibility that the password would be intercepted, clients should connect to MySQL Server using a secure connection. See Section 6.1.7, "The Cleartext Client-Side Authentication Plugin".

To refer to the PAM authentication plugin in the IDENTIFIED WITH clause of a CREATE USER or GRANT statement, use the name authentication_pam. For example:

```
CREATE USER user

IDENTIFIED WITH authentication_pam

AS 'authentication_string';
```

The authentication string specifies the following types of information:

- PAM supports the notion of "service name," which is a name that the system administrator can use to
 configure the authentication method for a particular application. There can be several such "applications"
 associated with a single database server instance, so the choice of service name is left to the SQL
 application developer. When you define an account that should authenticate using PAM, specify the
 service name in the authentication string.
- PAM provides a way for a PAM module to return to the server a MySQL user name other than the login name supplied at login time. Use the authentication string to control the mapping between login name and MySQL user name. If you want to take advantage of proxy user capabilities, the authentication string must include this kind of mapping.

For example, if the service name is mysql and users in the root and users PAM groups should be mapped to the developer and data_entry MySQL users, respectively, use a statement like this:

```
CREATE USER user

IDENTIFIED WITH authentication_pam

AS 'mysql, root=developer, users=data_entry';
```

Authentication string syntax for the PAM authentication plugin follows these rules:

The string consists of a PAM service name, optionally followed by a group mapping list consisting of one
or more keyword/value pairs each specifying a group name and a MySQL user name:

```
pam_service_name[,group_name=mysql_user_name]...
```

The plugin parses the authentication string on each login check. To minimize overhead, keep the string as short as possible.

- Each group_name=mysql_user_name pair must be preceded by a comma.
- Leading and trailing spaces not inside double quotation marks are ignored.
- Unquoted pam_service_name, group_name, and mysql_user_name values can contain anything except equal sign, comma, or space.
- If a pam_service_name, group_name, or mysql_user_name value is quoted with double quotation
 marks, everything between the quotation marks is part of the value. This is necessary, for example, if the
 value contains space characters. All characters are legal except double quotation mark and backslash
 (\). To include either character, escape it with a backslash.

If the plugin successfully authenticates a login name, it looks for a group mapping list in the authentication string and, if present, uses it to return a different user name to the MySQL server based on the groups the external user is a member of:

- If the authentication string contains no group mapping list, the plugin returns the login name.
- If the authentication string does contain a group mapping list, the plugin examines each group_name=mysql_user_name pair in the list from left to right and tries to find a match for the group_name value in a non-MySQL directory of the groups assigned to the authenticated user and returns mysql_user_name for the first match it finds. If the plugin finds no match for any group, it returns the login name. If the plugin is not capable of looking up a group in a directory, it ignores the group mapping list and returns the login name.

The following sections describe how to set up several authentication scenarios that use the PAM authentication plugin:

• No proxy users. This uses PAM only to check login names and passwords. Every external user permitted to connect to MySQL Server should have a matching MySQL account that is defined to use external PAM authentication. (For a MySQL account of user_name must be the login name and host_name must from which the client connects.) Authentication can be performed by various PAM-supported methods. The discussion shows how to use traditional Unix passwords and LDAP.

PAM authentication, when not done through proxy users or groups, requires the MySQL account to have the same user name as the Unix account. Because MySQL user names are limited to 16 characters (see Section 4.2, "Grant Tables"), this limits PAM nonproxy authentication to Unix accounts with names of at most 16 characters.

Proxy login only and group mapping. For this scenario, create one or a few MySQL accounts that
define different sets of privileges. (Ideally, nobody should connect using those accounts directly.) Then

define a default user authenticating through PAM that uses some mapping scheme (usually by the external groups the users are in) to map all the external logins to the few MySQL accounts holding the privilege sets. Any user that logs in is mapped to one of the MySQL accounts and uses its privileges. The discussion shows how to set this up using Unix passwords, but other PAM methods such as LDAP could be used instead.

Variations on these scenarios are possible. For example, you can permit some users to log in directly (without proxying) but require others to connect through proxy users.

The examples make the following assumptions. You might need to make some adjustments if your system is set up differently.

- The PAM configuration directory is /etc/pam.d.
- The PAM service name is mysql, which means that you must set up a PAM file named mysql in the PAM configuration directory (creating the file if it does not exist). If you use a service name different from mysql, the file name will be different and you must use a different name in the AS 'auth_string' clause of CREATE USER and GRANT statements.
- The examples use a login name of antonio and password of verysecret. Change these to correspond to the users you want to authenticate.

The PAM authentication plugin checks at initialization time whether the AUTHENTICATION_PAM_LOG environment value is set in the server's startup environment. If so, the plugin enables logging of diagnostic messages to the standard output. Depending on how your server is started, the message might appear on the console or in the error log. These messages can be helpful for debugging PAM-related problems that occur when the plugin performs authentication. For more information, see Section 6.1.5.6, "PAM Authentication Plugin Debugging".

6.1.5.3 Unix Password Authentication without Proxy Users

This authentication scenario uses PAM only to check Unix user login names and passwords. Every external user permitted to connect to MySQL Server should have a matching MySQL account that is defined to use external PAM authentication.

- 1. Verify that Unix authentication in PAM permits you to log in as antonio with password very secret.
- 2. Set up PAM to authenticate the <code>mysql</code> service by creating a file named <code>/etc/pam.d/mysql</code>. The file contents are system dependent, so check existing login-related files in the <code>/etc/pam.d</code> directory to see what they look like. On Linux, the <code>mysql</code> file might look like this:

```
#%PAM-1.0
auth include password-auth
account include password-auth
```

For Gentoo Linux, use system-login rather than password-auth. For OS X, use login rather than password-auth.

On Ubuntu and other Debian-based systems, use these file contents instead:

```
@include common-auth
@include common-account
@include common-session-noninteractive
```

3. Create a MySQL account with the same user name as the Unix login name and define it to authenticate using the PAM plugin:

```
CREATE USER 'antonio'@'localhost'
IDENTIFIED WITH authentication_pam AS 'mysql';
GRANT ALL PRIVILEGES ON mydb.* TO 'antonio'@'localhost';
```

4. Connect to the MySQL server using the mysql command-line client. For example:

```
mysql --user=antonio --password=verysecret --enable-cleartext-plugin mydb
```

The server should permit the connection and the following query should return output as shown:

This demonstrates that antonio uses the privileges granted to the antonio MySQL account, and that no proxying has occurred.

6.1.5.4 LDAP Authentication without Proxy Users

This authentication scenario uses PAM only to check LDAP user login names and passwords. Every external user permitted to connect to MySQL Server should have a matching MySQL account that is defined to use external PAM authentication.

- 1. Verify that LDAP authentication in PAM permits you to log in as antonio with password verysecret.
- 2. Set up PAM to authenticate the mysql service through LDAP by creating a file named /etc/pam.d/mysql. The file contents are system dependent, so check existing login-related files in the /etc/pam.d directory to see what they look like. On Linux, the mysql file might look like this:

```
#%PAM-1.0
auth required pam_ldap.so
account required pam_ldap.so
```

If PAM object files have a suffix different from . so on your system, substitute the correct suffix.

The PAM file might have a different format on some systems.

3. MySQL account creation and connecting to the server is the same as previously described in Section 6.1.5.3, "Unix Password Authentication without Proxy Users".

6.1.5.5 Unix Password Authentication with Proxy Users and Group Mapping

This authentication scheme uses proxying and group mapping to map users who connect to the MySQL server through PAM onto MySQL accounts that define different sets of privileges. Users do not connect directly through the accounts that define the privileges. Instead, they connect through a default proxy user authenticating through PAM that uses a mapping scheme to map all the external logins to the few MySQL accounts holding the privileges. Any user who connects is mapped to one of the MySQL accounts and uses its privileges.

The procedure shown here uses Unix password authentication. To use LDAP instead, see the early steps of Section 6.1.5.4, "LDAP Authentication without Proxy Users".

- 1. Verify that Unix authentication in PAM permits you to log in as antonio with password verysecret and that antonio is a member of the root or users group.
- 2. Set up PAM to authenticate the mysql service. Put the following in /etc/pam.d/mysql:

```
#%PAM-1.0
auth include password-auth
account include password-auth
```

use system-login rather than password-auth. For OS X, use login rather than password-auth.

The PAM file might have a different format on some systems. For example, on Ubuntu and other Debian-based systems, use these file contents instead:

```
@include common-auth
@include common-account
@include common-session-noninteractive
```

3. Create a default proxy user (''@'') that maps the external PAM users to the proxied accounts. It maps external users from the root PAM group to the developer MySQL account and the external users from the users PAM group to the data_entry MySQL account:

```
CREATE USER ''@''

IDENTIFIED WITH authentication_pam

AS 'mysql, root=developer, users=data_entry';
```

The mapping list following the service name is required when you set up proxy users. Otherwise, the plugin cannot tell how to map the name of PAM groups to the proper proxied user name.

If your MySQL installation has anonymous users, they might conflict with the default proxy user. For more information about this problem, and ways of dealing with it, see Default Proxy User and Anonymous User Conflicts.

4. Create the proxied accounts that will be used to access the databases:

```
CREATE USER 'developer'@'localhost' IDENTIFIED BY 'very secret password';
GRANT ALL PRIVILEGES ON mydevdb.* TO 'developer'@'localhost';
CREATE USER 'data_entry'@'localhost' IDENTIFIED BY 'very secret password';
GRANT ALL PRIVILEGES ON mydb.* TO 'data_entry'@'localhost';
```

If you do not let anyone know the passwords for these accounts, other users cannot use them to connect directly to the MySQL server. Instead, it is expected that users will authenticate using PAM and that they will use the developer or data_entry account by proxy based on their PAM group.

5. Grant the PROXY privilege to the proxy account for the proxied accounts:

```
GRANT PROXY ON 'developer'@'localhost' TO ''@'';
GRANT PROXY ON 'data_entry'@'localhost' TO ''@'';
```

6. Connect to the MySQL server using the mysql command-line client. For example:

```
mysql --user=antonio --password=verysecret --enable-cleartext-plugin mydb
```

The server authenticates the connection using the ''@'' account. The privileges antonio will have depends on what PAM groups he is a member of. If antonio is a member of the root PAM group,

the PAM plugin maps root to the developer MySQL user name and returns that name to the server. The server verifies that ''@'' has the PROXY privilege for developer and permits the connection. the following query should return output as shown:

This demonstrates that antonio uses the privileges granted to the developer MySQL account, and that proxying occurred through the default proxy user account.

If antonio is not a member of the root PAM group but is a member of the users group, a similar process occurs, but the plugin maps user group membership to the data_entry MySQL user name and returns that name to the server. In this case, antonio uses the privileges of the data_entry MySQL account:

6.1.5.6 PAM Authentication Plugin Debugging

The PAM authentication plugin checks at initialization time whether the AUTHENTICATION_PAM_LOG environment value is set (the value does not matter). If so, the plugin enables logging of diagnostic messages to the standard output. These messages may be helpful for debugging PAM-related problems that occur when the plugin performs authentication.

Some messages include reference to PAM plugin source files and line numbers, which enables plugin actions to be tied more closely to the location in the code where they occur.

The following transcript demonstrates the kind of information produced by enabling logging. It resulted from a successful proxy authentication attempt.

```
entering auth_pam_server
entering auth_pam_next_token
auth_pam_next_token:reading at [cups,admin=writer,everyone=reader], sep=[,]
auth_pam_next_token:state=PRESPACE, ptr=[cups,admin=writer,everyone=reader],
out=[]
auth_pam_next_token:state=IDENT, ptr=[cups,admin=writer,everyone=reader],
auth_pam_next_token:state=AFTERSPACE, ptr=[,admin=writer,everyone=reader],
out=[cups]
auth_pam_next_token:state=DELIMITER, ptr=[,admin=writer,everyone=reader],
out=[cups]
auth_pam_next_token:state=DONE, ptr=[,admin=writer,everyone=reader],
out=[cups]
leaving auth_pam_next_token on
auth_pam_server:password 12345qq received
auth pam server:pam start rc=0
auth_pam_server:pam_set_item(PAM_RUSER,gkodinov) rc=0
auth_pam_server:pam_set_item(PAM_RHOST,localhost) rc=0
entering auth_pam_server_conv
```

```
auth_pam_server_conv:PAM_PROMPT_ECHO_OFF [Password:] received
leaving auth_pam_server_conv on
/Users/gkodinov/mysql/work/x-5.5.16-release-basket/release/plugin/pam-authentication-plugin/src/authentication
auth_pam_server:pam_authenticate rc=0
auth_pam_server:pam_acct_mgmt rc=0
auth_pam_server:pam_setcred(PAM_ESTABLISH_CRED) rc=0
auth_pam_server:pam_get_item rc=0
auth_pam_server:pam_setcred(PAM_DELETE_CRED) rc=0
entering auth_pam_map_groups
entering auth_pam_walk_namevalue_list
auth_pam_walk_namevalue_list:reading at: [admin=writer,everyone=reader]
entering auth_pam_next_token
auth_pam_next_token:reading at [admin=writer,everyone=reader], sep=[=]
auth_pam_next_token:state=PRESPACE, ptr=[admin=writer,everyone=reader], out=[]
auth_pam_next_token:state=IDENT, ptr=[admin=writer,everyone=reader], out=[]
auth_pam_next_token:state=AFTERSPACE, ptr=[=writer,everyone=reader],
out=[admin]
auth_pam_next_token:state=DELIMITER, ptr=[=writer,everyone=reader],
out=[admin]
auth_pam_next_token:state=DONE, ptr=[=writer,everyone=reader], out=[admin]
leaving auth_pam_next_token on
/Users/gkodinov/mysql/work/x-5.5.16-release-basket/release/plugin/pam-authentication-plugin/src/parser.c:191
auth_pam_walk_namevalue_list:name=[admin]
entering auth_pam_next_token
auth_pam_next_token:reading at [writer,everyone=reader], sep=[,]
auth_pam_next_token:state=PRESPACE, ptr=[writer,everyone=reader], out=[]
auth_pam_next_token:state=IDENT, ptr=[writer,everyone=reader], out=[]
auth_pam_next_token:state=AFTERSPACE, ptr=[,everyone=reader], out=[writer]
auth_pam_next_token:state=DELIMITER, ptr=[,everyone=reader], out=[writer]
auth_pam_next_token:state=DONE, ptr=[,everyone=reader], out=[writer]
leaving auth_pam_next_token on
walk, &error_namevalue_list:value=[writer]
entering auth_pam_map_group_to_user
auth_pam_map_group_to_user:pam_user=gkodinov, name=admin, value=writer
examining member root
examining member gkodinov
substitution was made to mysql user writer
leaving auth_pam_map_group_to_user on
/Users/gkodinov/mysql/work/x-5.5.16-release-basket/release/plugin/pam-authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/sr
auth_pam_walk_namevalue_list:found mapping
leaving auth_pam_walk_namevalue_list on
/Users/gkodinov/mysql/work/x-5.5.16-release-basket/release/plugin/pam-authentication-plugin/src/parser.c: 270-basket/release/plugin/pam-authentication-plugin/src/parser.c: 270-basket/release/plugin/pam-authentication-plugin/src/parser.c: 270-basket/release/plugin/pam-authentication-plugin/src/parser.c: 270-basket/release/plugin/pam-authentication-plugin/src/parser.c: 270-basket/release/plugin/pam-authentication-plugin/src/parser.c: 270-basket/release/plugin/pam-authentication-plugin/src/parser.c: 270-basket/release/plugin/src/parser.c: 270-basket/release/plu
auth_pam_walk_namevalue_list returned 0
leaving auth_pam_map_groups on
/Users/gkodinov/mysql/work/x-5.5.16-release-basket/release/plugin/pam-authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/src/authentication-plugin/sr
auth pam server:authenticated as=writer
auth_pam_server: rc=0
leaving auth_pam_server on
/Users/gkodinov/mysgl/work/x-5.5.16-release-basket/release/plugin/pam-authentication-plugin/src/authentication
```

6.1.6 The Windows Native Authentication Plugin

Note

The Windows authentication plugin is an extension included in MySQL Enterprise Edition, a commercial product. To learn more about commercial products, see http://www.mysql.com/products/.

As of MySQL 5.6.10, MySQL Enterprise Edition for Windows includes an authentication plugin that performs external authentication on Windows, enabling MySQL Server to use native Windows services to authenticate client connections. Users who have logged in to Windows can connect from MySQL client programs to the server based on the information in their environment without specifying an additional password.

The client and server exchange data packets in the authentication handshake. As a result of this exchange, the server creates a security context object that represents the identity of the client in the Windows OS. This identity includes the name of the client account. The Windows authentication plugin uses the identity of the client to check whether it is a given account or a member of a group. By default, negotiation uses Kerberos to authenticate, then NTLM if Kerberos is unavailable.

The Windows authentication plugin provides these capabilities:

- External authentication: The plugin enables MySQL Server to accept connections from users defined outside the MySQL grant tables.
- Proxy user support: The plugin can return to MySQL a user name different from the client user. This
 means that the plugin can return the MySQL user that defines the privileges the external Windowsauthenticated user should have. For example, a Windows user named joe can connect and have the
 privileges of the MySQL user named developer.

The following table shows the plugin and library file names. The file location must be the directory named by the plugin_dir system variable. For installation information, see Section 6.1.6.1, "Installing the Windows Authentication Plugin".

Table 6.5 MySQL Windows Authentication Plugin

Server-side plugin name authentication_windows		
Client-side plugin name	authentication_windows_client	
Library file name	authentication_windows.dll	

The library file includes only the server-side plugin. The client-side plugin is built into the libmysqlclient client library.

The server-side Windows authentication plugin is included only in MySQL Enterprise Edition. It is not included in MySQL community distributions. The client-side plugin is included in all distributions, including community distributions. This permits clients from any distribution to connect to a server that has the server-side plugin loaded.

The Windows authentication plugin is supported on any version of Windows supported by MySQL 5.6 (see http://www.mysql.com/support/supportedplatforms/database.html). It requires MySQL Server 5.6.10 or higher.

For general information about pluggable authentication in MySQL, see Section 5.7, "Pluggable Authentication". For proxy user information, see Section 5.8, "Proxy Users".

6.1.6.1 Installing the Windows Authentication Plugin

This section describes how to install the Windows authentication plugin. For general information about installing plugins, see Installing and Uninstalling Plugins.

To be usable by the server, the plugin library file must be located in the MySQL plugin directory (the directory named by the plugin_dir system variable). If necessary, set the value of plugin_dir at server startup to tell the server the location of the plugin directory.

To enable the plugin, start the server with the --plugin-load option. For example, put these lines in your my.ini file:

```
[mysqld]
plugin-load=authentication_windows.dll
```

To verify plugin installation, examine the INFORMATION_SCHEMA.PLUGINS table or use the SHOW PLUGINS statement (see Obtaining Server Plugin Information). For example:

To associate a MySQL account with the Windows authentication plugin, use the plugin name authentication_windows in the IDENTIFIED WITH clause of CREATE USER or GRANT statement that creates the account.

6.1.6.2 Using the Windows Authentication Plugin

The Windows authentication plugin supports the use of MySQL accounts such that users who have logged in to Windows can connect to the MySQL server without having to specify an additional password. It is assumed that the server-side plugin is enabled, as described previously. Once the DBA has enabled the server-side plugin and set up accounts to use it, clients can connect using those accounts with no other setup required on their part.

To refer to the Windows authentication plugin in the IDENTIFIED WITH clause of a CREATE USER or GRANT statement, use the name authentication_windows. Suppose that the Windows users Rafal and Tasha should be permitted to connect to MySQL, as well as any users in the Administrators or Power Users group. To set this up, create a MySQL account named sql_admin that uses the Windows plugin for authentication:

```
CREATE USER sql_admin
IDENTIFIED WITH authentication_windows
AS 'Rafal, Tasha, Administrators, "Power Users"';
```

The plugin name is authentication_windows. The string following the AS keyword is the authentication string. It specifies that the Windows users named Rafal or Tasha are permitted to authenticate to the server as the MySQL user sql_admin, as are any Windows users in the Administrators or Power Users group. The latter group name contains a space, so it must be quoted with double quote characters.

After you create the sql_admin account, a user who has logged in to Windows can attempt to connect to the server using that account:

```
C:\> mysql --user=sql_admin
```

No password is required here. The authentication_windows plugin uses the Windows security API to check which Windows user is connecting. If that user is named Rafal or Tasha, or is in the Administrators or Power Users group, the server grants access and the client is authenticated as sql_admin and has whatever privileges are granted to the sql_admin account. Otherwise, the server denies access.

Authentication string syntax for the Windows authentication plugin follows these rules:

- The string consists of one or more user mappings separated by commas.
- Each user mapping associates a Windows user or group name with a MySQL user name:

```
win_user_or_group_name=mysql_user_name
win_user_or_group_name
```

For the latter syntax, with no <code>mysql_user_name</code> value given, the implicit value is the MySQL user created by the <code>CREATE USER</code> statement. Thus, these statements are equivalent:

```
CREATE USER sql_admin

IDENTIFIED WITH authentication_windows

AS 'Rafal, Tasha, Administrators, "Power Users"';

CREATE USER sql_admin

IDENTIFIED WITH authentication_windows

AS 'Rafal=sql_admin, Tasha=sql_admin, Administrators=sql_admin,

"Power Users"=sql_admin';
```

- Each backslash ('\') in a value must be doubled because backslash is the escape character in MySQL strings.
- Leading and trailing spaces not inside double quotation marks are ignored.
- Unquoted win_user_or_group_name and mysql_user_name values can contain anything except equal sign, comma, or space.
- If a win_user_or_group_name and or mysql_user_name value is quoted with double quotation marks, everything between the quotation marks is part of the value. This is necessary, for example, if the name contains space characters. All characters within double quotes are legal except double quotation mark and backslash. To include either character, escape it with a backslash.
- win_user_or_group_name values use conventional syntax for Windows principals, either local or in a
 domain. Examples (note the doubling of backslashes):

```
domain\\user
.\\user
domain\\group
.\\group
BUILTIN\\WellKnownGroup
```

When invoked by the server to authenticate a client, the plugin scans the authentication string left to right for a user or group match to the Windows user. If there is a match, the plugin returns the corresponding <code>mysql_user_name</code> to the MySQL server. If there is no match, authentication fails.

A user name match takes preference over a group name match. Suppose that the Windows user named win user is a member of win group and the authentication string looks like this:

```
'win_group = sql_user1, win_user = sql_user2'
```

When win_user connects to the MySQL server, there is a match both to win_group and to win_user. The plugin authenticates the user as sql_user2 because the more-specific user match takes precedence over the group match, even though the group is listed first in the authentication string.

Windows authentication always works for connections from the same computer on which the server is running. For cross-computer connections, both computers must be registered with Windows Active Directory. If they are in the same Windows domain, it is unnecessary to specify a domain name. It is also possible to permit connections from a different domain, as in this example:

```
CREATE USER sql_accounting
IDENTIFIED WITH authentication_windows
AS 'SomeDomain\\Accounting';
```

Here SomeDomain is the name of the other domain. The backslash character is doubled because it is the MySQL escape character within strings.

MySQL supports the concept of proxy users whereby a client can connect and authenticate to the MySQL server using one account but while connected has the privileges of another account (see Section 5.8, "Proxy Users"). Suppose that you want Windows users to connect using a single user name but be mapped based on their Windows user and group names onto specific MySQL accounts as follows:

- The local_user and MyDomain\domain_user local and domain Windows users should map to the local_wlad MySQL account.
- Users in the MyDomain\Developers domain group should map to the local_dev MySQL account.
- Local machine administrators should map to the local admin MySQL account.

To set this up, create a proxy account for Windows users to connect to, and configure this account so that users and groups map to the appropriate MySQL accounts (local_wlad, local_dev, local_admin). In addition, grant the MySQL accounts the privileges appropriate to the operations they need to perform. The following instructions use win_proxy as the proxy account, and local_wlad, local_dev, and local_admin as the proxied accounts.

1. Create the proxy MySQL account:

```
CREATE USER win_proxy

IDENTIFIED WITH authentication_windows

AS 'local_user = local_wlad,

MyDomain\\domain_user = local_wlad,

MyDomain\\Developers = local_dev,

BUILTIN\\Administrators = local_admin';
```

2. For proxying to work, the proxied accounts must exist, so create them:

```
CREATE USER local_wlad IDENTIFIED BY 'wlad_pass';
CREATE USER local_dev IDENTIFIED BY 'dev_pass';
CREATE USER local_admin IDENTIFIED BY 'admin_pass';
```

If you do not let anyone know the passwords for these accounts, other users cannot use them to connect directly to the MySQL server.

You should also issue GRANT statements (not shown) that grant each proxied account the privileges it needs.

3. The proxy account must have the PROXY privilege for each of the proxied accounts:

```
GRANT PROXY ON local_wlad TO win_proxy;
GRANT PROXY ON local_dev TO win_proxy;
GRANT PROXY ON local_admin TO win_proxy;
```

Now the Windows users <code>local_user</code> and <code>MyDomain_user</code> can connect to the MySQL server as <code>win_proxy</code> and when authenticated have the privileges of the account given in the authentication string—in this case, <code>local_wlad</code>. A user in the <code>MyDomain_Developers</code> group who connects as <code>win_proxy</code> has the privileges of the <code>local_dev</code> account. A user in the <code>BUILTIN_Administrators</code> group has the privileges of the <code>local_admin</code> account.

To configure authentication so that all Windows users who do not have their own MySQL account go through a proxy account, substitute the default proxy user (''@'') for win_proxy in the preceding instructions. For information about the default proxy user, see Section 5.8, "Proxy Users".

If your MySQL installation has anonymous users, they might conflict with the default proxy user. For more information about this problem, and ways of dealing with it, see Default Proxy User and Anonymous User Conflicts.

To use the Windows authentication plugin with Connector/Net connection strings in Connection/Net 6.4.4 and higher, see Using the Windows Native Authentication Plugin.

Additional control over the Windows authentication plugin is provided by the authentication_windows_use_principal_name and authentication_windows_log_level system variables. See Server System Variables.

6.1.7 The Cleartext Client-Side Authentication Plugin

As of MySQL 5.6.2, a client-side authentication plugin is available that sends the password to the server without hashing or encryption. This plugin is built into the MySQL client library.

The following table shows the plugin name.

Table 6.6 MySQL Cleartext Authentication Plugin

Server-side plugin name	None, see discussion	
Client-side plugin name	mysql_clear_password	
Library file name	None (plugin is built in)	

With native MySQL authentication, the client performs one-way hashing on the password before sending it to the server. This enables the client to avoid sending the password in clear text. See Section 2.2.4, "Password Hashing in MySQL". However, because the hash algorithm is one way, the original password cannot be recovered on the server side.

One-way hashing cannot be done for authentication schemes that require the server to receive the password as entered on the client side. In such cases, the <code>mysql_clear_password</code> client-side plugin can be used to send the password to the server in clear text. There is no corresponding server-side plugin. Rather, the client-side plugin can be used by any server-side plugin that needs a clear text password. (The PAM authentication plugin is one such; see Section 6.1.5, "The PAM Authentication Plugin".)

For general information about pluggable authentication in MySQL, see Section 5.7, "Pluggable Authentication".

Note

Sending passwords in clear text may be a security problem in some configurations. To avoid problems if there is any possibility that the password would be intercepted, clients should connect to MySQL Server using a method that protects the password. Possibilities include SSL (see Section 5.9, "Using Secure Connections"), IPsec, or a private network.

As of MySQL 5.6.7, to make inadvertent use of this plugin less likely, it is required that clients explicitly enable it. This can be done several ways:

- Set the LIBMYSQL_ENABLE_CLEARTEXT_PLUGIN environment variable to a value that begins with 1, y, or y. This enables the plugin for all client connections.
- The mysql, mysqladmin, and mysqlslap client programs support an --enable-cleartext-plugin option that enables the plugin on a per-invocation basis.
- The mysql_options() C API function supports a MYSQL_ENABLE_CLEARTEXT_PLUGIN option that enables the plugin on a per-connection basis. Also, any program that uses libmysqlclient and reads option files can enable the plugin by including an enable-cleartext-plugin option in an option group read by the client library.

6.1.8 The Socket Peer-Credential Authentication Plugin

As of MySQL 5.6.2, a server-side authentication plugin is available that authenticates clients that connect from the local host through the Unix socket file.

The source code for this plugin can be examined as a relatively simple example demonstrating how to write a loadable authentication plugin.

The following table shows the plugin and library file names. The file name suffix might differ on your system. The file location is the directory named by the plugin_dir system variable. For installation information, see Section 5.7, "Pluggable Authentication".

Table 6.7 MySQL Socket Peer-Credential Authentication Plugin

Server-side plugin name	auth_socket	
Client-side plugin name	None, see discussion	
Library file name	auth_socket.so	

The auth_socket authentication plugin authenticates clients that connect from the local host through the Unix socket file. The plugin uses the SO_PEERCRED socket option to obtain information about the user running the client program. Thus, the plugin can be built only on systems that support the SO_PEERCRED option, such as Linux.

The plugin checks whether the user name matches the MySQL user name specified by the client program to the server, and permits the connection only if the names match.

Suppose that a MySQL account is created for a user named valerie who is to be authenticated by the auth_socket plugin for connections from the local host through the socket file:

```
CREATE USER 'valerie'@'localhost' IDENTIFIED WITH auth_socket;
```

If a user on the local host with a login name of stefanie invokes mysql with the option -user=valerie to connect through the socket file, the server uses auth_socket to authenticate the
client. The plugin determines that the --user option value (valerie) differs from the client user's name
(stephanie) and refuses the connection. If a user named valerie tries the same thing, the plugin finds
that the user name and the MySQL user name are both valerie and permits the connection. However,
the plugin refuses the connection even for valerie if the connection is made using a different protocol,
such as TCP/IP.

For general information about pluggable authentication in MySQL, see Section 5.7, "Pluggable Authentication".

6.1.9 The Test Authentication Plugin

MySQL includes a test plugin that authenticates using MySQL native authentication, but is a loadable plugin (not built in) and must be installed prior to use. It can authenticate against either normal or older (shorter) password hash values.

This plugin is intended for testing and development purposes, and not for use in production environments. The test plugin source code is separate from the server source, unlike the built-in native plugin, so it can be examined as a relatively simple example demonstrating how to write a loadable authentication plugin.

The following table shows the plugin and library file names. The file name suffix might differ on your system. The file location is the directory named by the plugin_dir system variable. For installation information, see Section 5.7, "Pluggable Authentication".

Table 6.8 MySQL Test Authentication Plugin

Server-side plugin name test_plugin_server		
Client-side plugin name	auth_test_plugin	
Library file name	auth_test_plugin.so	

Because the test plugin authenticates the same way as native MySQL authentication, provide the usual --user and --password options that you normally use for accounts that use native authentication when you connect to the server. For example:

```
shell> mysql --user=your_name --password=your_pass
```

For general information about pluggable authentication in MySQL, see Section 5.7, "Pluggable Authentication".

6.2 The Password Validation Plugin

The validate_password plugin (available as of MySQL 5.6.6) can be used to test passwords and improve security. This plugin implements two capabilities:

- In statements that assign a password supplied as a cleartext value, the value is checked against the current password policy and rejected if it is weak (the statement returns an ER_NOT_VALID_PASSWORD error). This affects the CREATE USER, GRANT, and SET PASSWORD statements. Passwords given as arguments to the PASSWORD() and OLD_PASSWORD() functions are checked as well.
- The strength of potential passwords can be assessed using the VALIDATE_PASSWORD_STRENGTH() SQL function, which takes a password argument and returns an integer from 0 (weak) to 100 (strong).

For example, the cleartext password in the following statement is checked. Under the default password policy, which requires passwords to be at least 8 characters long, the password is weak and the statement produces an error:

```
mysql> SET PASSWORD = PASSWORD('abc');
ERROR 1819 (HY000): Your password does not satisfy the current policy
requirements
```

Passwords specified as already hashed values are not checked because the original password value is not available:

```
mysql> SET PASSWORD = '*0D3CED9BEC10A777AEC23CCC353A8C08A633045E';
Query OK, 0 rows affected (0.01 sec)
```

The parameters that control password checking are available as the values of the system variables having names of the form validate_password_xxx. These variables can be modified to configure password checking; see Section 6.2.2, "Password Validation Plugin Options and Variables".

The three levels of password checking are LOW, MEDIUM, and STRONG. The default is MEDIUM; to change this, modify the value of validate_password_policy. The policies implement increasingly strict password tests. The following descriptions refer to default parameter values; these can be modified by changing the appropriate system variables.

- LOW policy tests password length only. Passwords must be at least 8 characters long.
- MEDIUM policy adds the conditions that passwords must contain at least 1 numeric character, 1 lowercase and uppercase character, and 1 special (nonalphanumeric) character.

• STRONG policy adds the condition that password substrings of length 4 or longer must not match words in the dictionary file, if one has been specified.

If the validate_password plugin is not installed, the validate_password_xxx system variables are not available, passwords in statements are not checked, and VALIDATE_PASSWORD_STRENGTH() always returns 0. For example, accounts can be assigned passwords shorter than 8 characters.

6.2.1 Password Validation Plugin Installation

This section describes how to install the password-validation plugin. For general information about installing plugins, see Installing and Uninstalling Plugins.

To be usable by the server, the plugin library file must be located in the MySQL plugin directory (the directory named by the plugin_dir system variable). If necessary, set the value of plugin_dir at server startup to tell the server the location of the plugin directory.

The plugin library file base name is validate_password. The file name suffix differs per platform (for example, .so for Unix and Unix-like systems, .dll for Windows).

To load the plugin at server startup, use the --plugin-load option to name the library file that contains the plugin. With this plugin-loading method, the option must be given each time the server starts. For example, put these lines in your my.cnf file (adjust the .so suffix for your platform as necessary):

```
[mysqld]
plugin-load=validate_password.so
```

Alternatively, to register the plugin at runtime, use this statement (adjust the extension as necessary):

```
INSTALL PLUGIN validate_password SONAME 'validate_password.so';
```

INSTALL PLUGIN loads the plugin, and also registers it in the mysql.plugins table to cause the plugin to be loaded for each subsequent normal server startup.

To verify plugin installation, examine the INFORMATION_SCHEMA.PLUGINS table or use the SHOW PLUGINS statement (see Obtaining Server Plugin Information). For example:

If the plugin has been previously registered with INSTALL PLUGIN or is loaded with --plugin-load, you can use the --validate-password option at server startup to control plugin activation. For example, to load the plugin at startup and prevent it from being removed at runtime, use these options:

```
[mysqld]
plugin-load=validate_password.so
validate-password=FORCE_PLUS_PERMANENT
```

If it is desired to prevent the server from running without the password-validation plugin, use -- validate-password with a value of FORCE or FORCE_PLUS_PERMANENT to force server startup to fail if the plugin does not initialize successfully.

6.2.2 Password Validation Plugin Options and Variables

To control the activation of the validate_password plugin, use this option:

• --validate-password[=value]

Introduced	5.6.6			
Command-Line Format	valid	validate-password[=value]		
Permitted Values	Type enumeration			
	Default	ON		
	Valid	ON		
	Values	OFF		
		FORCE		
		FORCE_PLUS_PERMANENT		

This option controls how the server loads the validate_password plugin at startup. The value should be one of those available for plugin-loading options, as described in Installing and Uninstalling Plugins. For example, --validate-password=FORCE_PLUS_PERMANENT tells the server to load the plugin at startup and prevents it from being removed while the server is running.

This option is available only if the validate_password plugin has been previously registered with INSTALL PLUGIN or is loaded with --plugin-load. See Section 6.2.1, "Password Validation Plugin Installation".

If the validate_password plugin is enabled, it exposes several system variables that indicate the parameters that control password checking:

mysql> SHOW VARIABLES LIKE 'validate_password%';		
Variable_name	Value	
validate_password_dictionary_file validate_password_length validate_password_mixed_case_count validate_password_number_count validate_password_policy validate_password_special_char_count	 8 1 1 MEDIUM 1	

To change how passwords are checked, you can set any of these variables at server startup, and most of them at runtime. The following list describes the meaning of each variable.

validate_password_dictionary_file

Introduced	5.6.6		
System Variable (<= 5.6.25)	Name	validate_password_dictionary_file	
	Variable Scope	Global	
	Dynamic Variable		
System Variable	Name	validate_password_dictionary_file	
	Variable Scope	Global	

	Dynamic Variable	
System Variable (>= 5.6.26)	Name	validate_password_dictionary_file
	Variable Scope	Global
	Dynamic Variable	
Permitted Values	Туре	file name

The path name of the dictionary file used by the validate_password plugin for checking passwords. This variable is unavailable unless that plugin is installed.

By default, this variable has an empty value and dictionary checks are not performed. To enable dictionary checks, you must set this variable to a nonempty value. If the file is named as a relative path, it is interpreted relative to the server data directory. Its contents should be lowercase, one word per line. Contents are treated as having a character set of utf8. The maximum permitted file size is 1MB.

For the dictionary file to be used during password checking, the password policy must be set to 2 (STRONG); see the description of the validate_password_policy system variable. Assuming that is true, each substring of the password of length 4 up to 100 is compared to the words in the dictionary file. Any match causes the password to be rejected. Comparisons are not case sensitive.

For VALIDATE_PASSWORD_STRENGTH() the password is checked against all policies, including STRONG, so the strength assessment includes the dictionary check regardless of the validate_password_policy value.

Before MySQL 5.6.26, changes to the dictionary file while the server is running require a restart for the server to recognize the changes. As of MySQL 5.6.26, validate_password_dictionary_file can be set at runtime and assigning a value causes the named file to be read without a restart.

• validate_password_length

Introduced	5.6.6	5.6.6		
System Variable	Name	validate_password_length		
	Variable Scope	Global		
	Dynamic Variable			
Permitted Values	Туре	integer		
	Default	8		
	Min Value	0		

The minimum number of characters that passwords checked by the validate_password plugin must have. This variable is unavailable unless that plugin is installed.

The validate_password_length minimum value is a function of several other related system variables. As of MySQL 5.6.10, the server will not set the value less than the value of this expression:

```
validate_password_number_count
+ validate_password_special_char_count
```

+ (2 * validate_password_mixed_case_count)

If the validate_password plugin adjusts the value of validate_password_length due to the preceding constraint, it writes a message to the error log.

validate_password_mixed_case_count

Introduced	5.6.6	5.6.6		
System Variable	Name	Name validate_password_mixed_case_count		
	Variable Scope	Global		
	Dynamic Variable			
Permitted Values	Туре	integer		
	Default	1		
	Min Value	0		

The minimum number of lowercase and uppercase characters that passwords checked by the validate_password plugin must have if the password policy is MEDIUM or stronger. This variable is unavailable unless that plugin is installed.

• validate_password_number_count

Introduced	5.6.6	5.6.6		
System Variable	Name	validate_password_number_count		
	Variable	Global		
	Scope			
	Dynamic Variable			
Permitted Values	Туре	integer		
	Default	1		
	Min Value	0		

The minimum number of numeric (digit) characters that passwords checked by the validate_password plugin must have if the password policy is MEDIUM or stronger. This variable is unavailable unless that plugin is installed.

validate_password_policy

Introduced	5.6.6	5.6.6	
System Variable	Name	validate_password_policy	
	Variable Scope	Global	
	Dynamic Variable	Yes	
Permitted Values	Туре	enumeration 123	

Default	1
	0
Values	1
	2

The password policy enforced by the validate_password plugin. This variable is unavailable unless that plugin is installed.

The validate_password_policy value can be specified using numeric values 0, 1, 2, or the corresponding symbolic values LOW, MEDIUM, STRONG. The following table describes the tests performed for each policy. For the length test, the required length is the value of the validate_password_length system variable. Similarly, the required values for the other tests are given by other validate_password_xxx variables.

Policy	Tests Performed	
0 or LOW	Length	
1 or MEDIUM	Length; numeric, lowercase/uppercase, and special characters	
2 or STRONG	Length; numeric, lowercase/uppercase, and special characters; dictionary file	

Note

Before MySQL 5.6.10, validate_password_policy was named validate_password_policy_number.

• validate_password_special_char_count

Introduced	5.6.6	5.6.6	
System Variable	Name	validate_password_special_char_count	
	Variable Scope	Global	
	Dynamic Variable		
Permitted Values	Туре	integer	
	Default	1	
	Min Value	0	

The minimum number of nonalphanumeric characters that passwords checked by the validate_password plugin must have if the password policy is MEDIUM or stronger. This variable is unavailable unless that plugin is installed.

If the validate_password plugin is enabled, it exposes several status variables that provide operational information:

The following list describes the meaning of each variable.

validate_password_dictionary_file_last_parsed

When the dictionary file was last parsed.

This variable was added in MySQL 5.6.26.

validate_password_dictionary_file_words_count

The number of words read from the dictionary file.

This variable was added in MySQL 5.6.26.

6.3 MySQL Enterprise Audit

Note

MySQL Enterprise Audit is an extension included in MySQL Enterprise Edition, a commercial product. To learn more about commercial products, see http://www.mysql.com/products/.

As of MySQL 5.6.10, MySQL Enterprise Edition includes MySQL Enterprise Audit, implemented using a server plugin named audit_log. MySQL Enterprise Audit uses the open MySQL Audit API to enable standard, policy-based monitoring and logging of connection and query activity executed on specific MySQL servers. Designed to meet the Oracle audit specification, MySQL Enterprise Audit provides an out of box, easy to use auditing and compliance solution for applications that are governed by both internal and external regulatory guidelines.

When installed, the audit plugin enables MySQL Server to produce a log file containing an audit record of server activity. The log contents include when clients connect and disconnect, and what actions they perform while connected, such as which databases and tables they access.

After you install the plugin (see Section 6.3.1, "Installing MySQL Enterprise Audit"), it writes an audit log file. By default, the file is named audit.log in the server data directory. To change the name of the file, set the audit_log_file system variable at server startup.

Audit log file contents are not encrypted. See Section 6.3.2, "MySQL Enterprise Audit Security Considerations".

The audit log file is written in XML, with auditable events encoded as <AUDIT_RECORD> elements. To select the file format, set the audit_log_format system variable at server startup. For details on file format and contents, see Section 6.3.3, "The Audit Log File".

For more information about controlling how logging occurs, see Section 6.3.4, "Audit Log Logging Control". To perform filtering of audited events, see Section 6.3.5, "Audit Log Filtering". For descriptions of the parameters used to configure the audit log plugin, see Section 6.3.6.2, "Audit Log Options and System Variables".

If the audit_log plugin is enabled, the Performance Schema (see MySQL Performance Schema) has instrumentation for the audit log plugin. To identify the relevant instruments, use this query:

```
SELECT NAME FROM performance_schema.setup_instruments WHERE NAME LIKE '%/alog/%';
```

Changes from Older MySQL Enterprise Audit Versions

Several changes were made to the audit log plugin in MySQL 5.6.14 for better compatibility with Oracle Audit Vault.

A new audit log file format was implemented. It is possible to select either the old or new format using the audit_log_format system variable, which has permitted values of OLD and NEW (default OLD). The two formats differ as follows:

- Information within <auDit_record> elements written in the old format using attributes is written in the new format using subelements.
- The new format includes more information in <audit_record> elements. Every element includes a record_id value providing a unique identifier. The TIMESTAMP value includes time zone information. Query records include HOST, IP, OS_LOGIN, and USER information, as well as COMMAND_CLASS and STATUS_CODE values.

Example of old <AUDIT_RECORD> format:

```
<AUDIT_RECORD
TIMESTAMP="2013-09-15T15:27:27"
NAME="Query"
CONNECTION_ID="3"
STATUS="0"
SQLTEXT="SELECT 1"
/>
```

Example of new <AUDIT_RECORD> format:

```
<AUDIT_RECORD>
<TIMESTAMP>2013-09-15T15:27:27 UTC</TIMESTAMP>
<RECORD_ID>3998_2013-09-15T15:27:27</RECORD_ID>
<NAME>Query</NAME>
<CONNECTION_ID>3</CONNECTION_ID>
<STATUS_O</STATUS>
<STATUS_CODE>0</STATUS_CODE>
<USER>root[root] @ localhost [127.0.0.1]</USER>
<OS_LOGIN></OS_LOGIN>
<HOST>localhost</HOST>
<IP>127.0.0.1</IP>
<COMMAND_CLASS>select</COMMAND_CLASS>
<SQLTEXT>SELECT 1</SQLTEXT>
</AUDIT_RECORD>
```

When the audit log plugin rotates the audit log file, it uses a different file name format. For a log file named audit.log, the plugin previously renamed the file to audit.log.TIMESTAMP. The plugin now renames the file to audit.log.TIMESTAMP.xml to indicate that it is an XML file.

If you change the value of audit_log_format, use this procedure to avoid writing log entries in one format to an existing log file that contains entries in a different format:

- 1. Stop the server.
- 2. Rename the current audit log file manually.
- 3. Restart the server with the new value of audit_log_format. The audit log plugin creates a new log file, which will contain log entries in the selected format.

The API for writing audit plugins has also changed. The mysql_event_general structure has new members to represent client host name and IP address, command class, and external user. For more information, see Writing Audit Plugins.

6.3.1 Installing MySQL Enterprise Audit

This section describes how to install MySQL Enterprise Audit, which is implemented using the audit_log plugin. For general information about installing plugins, see Installing and Uninstalling Plugins.

Note

If installed, the audit_log plugin involves some minimal overhead even when disabled. To avoid this overhead, do not install MySQL Enterprise Audit unless you plan to use it.

To be usable by the server, the plugin library file must be located in the MySQL plugin directory (the directory named by the plugin_dir system variable). If necessary, set the value of plugin_dir at server startup to tell the server the location of the plugin directory.

The plugin library file base name is audit_log. The file name suffix differs per platform (for example, .so for Unix and Unix-like systems, .dll for Windows).

To load the plugin at server startup, use the --plugin-load option to name the library file that contains the plugin. With this plugin-loading method, the option must be given each time the server starts. For example, put the following lines in your my.cnf file (adjust the .so suffix for your platform as necessary):

```
[mysqld]
plugin-load=audit_log.so
```

Alternatively, to register the plugin at runtime, use this statement (adjust the suffix as necessary):

```
INSTALL PLUGIN audit_log SONAME 'audit_log.so';
```

INSTALL PLUGIN loads the plugin, and also registers it in the mysql.plugins table to cause the plugin to be loaded for each subsequent normal server startup.

To verify plugin installation, examine the INFORMATION_SCHEMA.PLUGINS table or use the SHOW PLUGINS statement (see Obtaining Server Plugin Information). For example:

If the plugin has been previously registered with INSTALL PLUGIN or is loaded with --plugin-load, you can use the --audit-log option at server startup to control plugin activation. For example, to load the plugin at startup and prevent it from being removed at runtime, use these options:

```
[mysqld]
plugin-load=audit_log.so
audit-log=FORCE_PLUS_PERMANENT
```

If it is desired to prevent the server from running without the audit plugin, use --audit-log with a value of FORCE or FORCE_PLUS_PERMANENT to force server startup to fail if the plugin does not initialize successfully.

For additional information about the parameters used to configure operation of the audit_log plugin, see Section 6.3.6.2, "Audit Log Options and System Variables".

Audit log file contents are not encrypted. See Section 6.3.2, "MySQL Enterprise Audit Security Considerations".

6.3.2 MySQL Enterprise Audit Security Considerations

Contents of the audit log file produced by the audit_log plugin are not encrypted and may contain sensitive information, such as the text of SQL statements. For security reasons, this file should be written to a directory accessible only to the MySQL server and users with a legitimate reason to view the log. The default file is audit.log in the data directory. This can be changed by setting the audit_log_file system variable at server startup.

6.3.3 The Audit Log File

Audit log file contents are not encrypted. See Section 6.3.2, "MySQL Enterprise Audit Security Considerations".

The audit log file is written as XML, using UTF-8 (up to 4 bytes per character). The root element is <AUDIT>. The closing </AUDIT> tag of the root element is written when the audit log plugin terminates, so the tag is not present in the file while the plugin is active.

The root element contains <audit=record> elements, each of which provides information about an audited event.

In MySQL 5.6.14, a new audit log file format was implemented for better compatibility with Oracle Audit Vault. It is possible to select either the old or new format using the audit_log_format system variable, which has permitted values of OLD and NEW (default OLD).

If you change the value of audit_log_format, use this procedure to avoid writing log entries in one format to an existing log file that contains entries in a different format:

- 1. Stop the server.
- 2. Rename the current audit log file manually.
- 3. Restart the server with the new value of audit_log_format. The audit log plugin will create a new log file, which will contain log entries in the selected format.

Here is a sample log file in the default (old) format, reformatted slightly for readability:

```
<?xml version="1.0" encoding="UTF-8"?>
<AUDIT>
 <AUDIT_RECORD
   TIMESTAMP="2012-08-02T14:52:12"
   NAME="Audit"
   SERVER_ID="1"
   VERSION="1"
   STARTUP_OPTIONS="--port=3306"
   OS VERSION="i686-Linux"
   MYSOL VERSION="5.6.10-log"/>
  <AUDIT RECORD
   TIMESTAMP="2012-08-02T14:52:41"
   NAME="Connect"
   CONNECTION_ID="1"
   STATUS="0"
   USER="root"
   PRIV_USER="root"
```

```
OS_LOGIN=""
   PROXY_USER=""
   HOST="localhost"
   IP="127.0.0.1"
   DB=""/>
 <AUDIT_RECORD
   TIMESTAMP="2012-08-02T14:53:45"
   NAME="Query"
   CONNECTION_ID="1"
   STATUS="0"
   SQLTEXT="INSERT INTO t1 () VALUES()"/>
 <AUDIT_RECORD
   TIMESTAMP="2012-08-02T14:53:51"
   NAME="Ouit"
   CONNECTION_ID="1"
   STATUS="0"/>
 <AUDIT_RECORD
   TIMESTAMP="2012-08-06T14:21:03"
   NAME="NoAudit"
   SERVER_ID="1"/>
</AUDIT>
```

Here is a sample log file in the new format, reformatted slightly for readability:

```
<?xml version="1.0" encoding="UTF-8"?>
<AUDIT>
<AUDIT_RECORD>
 <TIMESTAMP>2013-09-17T15:03:24 UTC</TIMESTAMP>
 <RECORD_ID>1_2013-09-17T15:03:24</recORD_ID>
 <NAME>Audit</NAME>
 <SERVER_ID>1</SERVER_ID>
 <VERSION>1</VERSION>
 <STARTUP_OPTIONS>/usr/local/mysql/bin/mysqld
   --socket=/usr/local/mysql/mysql.sock
    --port=3306</STARTUP_OPTIONS>
 <OS_VERSION>x86_64-osx10.6</OS_VERSION>
 <MYSQL_VERSION>5.7.2-m12-log</MYSQL_VERSION>
</AUDIT_RECORD>
<AUDIT_RECORD>
 <TIMESTAMP>2013-09-17T15:03:40 UTC</TIMESTAMP>
 <RECORD_ID>2_2013-09-17T15:03:24</recORD_ID>
 <NAME>Connect</NAME>
 <CONNECTION_ID>2</CONNECTION_ID>
 <STATUS>0</STATUS>
 <STATUS_CODE>0</STATUS_CODE>
 <USER>root</USER>
  <OS_LOGIN></OS_LOGIN>
 <HOST>localhost</HOST>
 <IP>127.0.0.1</IP>
 <COMMAND_CLASS>connect</COMMAND_CLASS>
 <PRIV_USER>root</PRIV_USER>
 <PROXY_USER></PROXY_USER>
 <DB>test</DB>
</AUDIT_RECORD>
<AUDIT_RECORD>
 <TIMESTAMP>2013-09-17T15:03:41 UTC</TIMESTAMP>
 <RECORD_ID>4_2013-09-17T15:03:24/RECORD_ID>
 <NAME>Query</NAME>
 <CONNECTION_ID>2</CONNECTION_ID>
 <STATUS>0</STATUS>
 <STATUS_CODE>0</STATUS_CODE>
  <USER>root[root] @ localhost [127.0.0.1]</USER>
 <OS_LOGIN></OS_LOGIN>
 <HOST>localhost</HOST>
 <IP>127.0.0.1</IP>
```

```
<COMMAND_CLASS>drop_table</COMMAND_CLASS>
 <SQLTEXT>DROP TABLE IF EXISTS t</SQLTEXT>
</AUDIT_RECORD>
<AUDIT_RECORD>
 <TIMESTAMP>2013-09-17T15:03:41 UTC</TIMESTAMP>
 <RECORD_ID>5_2013-09-17T15:03:24/RECORD_ID>
 <NAME>Query</NAME>
 <CONNECTION_ID>2</CONNECTION_ID>
 <STATUS>0</STATUS>
 <STATUS_CODE>0</STATUS_CODE>
 <USER>root[root] @ localhost [127.0.0.1]</USER>
 <OS_LOGIN></OS_LOGIN>
 <hOST>localhost</hOST>
 <IP>127.0.0.1</IP>
 <COMMAND_CLASS>create_table</COMMAND_CLASS>
 <SQLTEXT>CREATE TABLE t (i INT)
</AUDIT_RECORD>
<AUDIT RECORD>
 <TIMESTAMP>2013-09-17T15:03:41 UTC</TIMESTAMP>
 <RECORD_ID>7_2013-09-17T15:03:24</recORD_ID>
 <NAME>Ouit</NAME>
 <CONNECTION_ID>2</CONNECTION_ID>
 <STATUS>0</STATUS>
 <STATUS_CODE>0</STATUS_CODE>
 <USER></USER>
 <OS_LOGIN></OS_LOGIN>
 <HOST></HOST>
 <IP></IP>
 <COMMAND_CLASS>connect</COMMAND_CLASS>
</AUDIT_RECORD>
<AUDIT RECORD>
 <TIMESTAMP>2013-09-17T15:03:47 UTC</TIMESTAMP>
 <RECORD_ID>9_2013-09-17T15:03:24</recORD_ID>
 <NAME>Shutdown</NAME>
 <CONNECTION_ID>3</CONNECTION_ID>
 <STATUS>0</STATUS>
 <STATUS_CODE>0</STATUS_CODE>
 <USER>root[root] @ localhost [127.0.0.1]</USER>
 <OS_LOGIN></OS_LOGIN>
 <HOST>localhost</HOST>
 <IP>127.0.0.1</IP>
 <COMMAND_CLASS></COMMAND_CLASS>
</AUDIT_RECORD>
<AUDIT_RECORD>
 <TIMESTAMP>2013-09-17T15:03:47 UTC</TIMESTAMP>
 <RECORD_ID>10_2013-09-17T15:03:24/RECORD_ID>
 <NAME>Ouit</NAME>
 <CONNECTION_ID>3</CONNECTION_ID>
 <STATUS>0</STATUS>
 <STATUS_CODE>0</STATUS_CODE>
 <USER></USER>
 <OS_LOGIN></OS_LOGIN>
 <HOST></HOST>
 <IP></IP>
 <COMMAND_CLASS>connect</COMMAND_CLASS>
</AUDIT_RECORD>
<AUDIT_RECORD>
 <TIMESTAMP>2013-09-17T15:03:49 UTC</TIMESTAMP>
 <RECORD_ID>11_2013-09-17T15:03:24</recORD_ID>
 <NAME>NoAudit</NAME>
 <SERVER_ID>1</SERVER_ID>
</AUDIT_RECORD>
</AUDIT>
```

Attributes of <audit_record> elements have these characteristics:

- Some attributes appear in every element, but most are optional and do not necessarily appear in every element.
- Order of attributes within an element is not guaranteed.
- Attribute values are not fixed length. Long values may be truncated as indicated in the attribute descriptions given later.
- The <, >, ", and & characters are encoded as <, >, ", and &, respectively. NUL bytes (U+00) are encoded as the? character.
- Characters not valid as XML characters are encoded using numeric character references. Valid XML characters are:

```
#x9 | #xA | #xD | [#x20-#xD7FF] | [#xE000-#xFFFD] | [#x10000-#x10FFFF]
```

New Audit Log File Format

Every <audit_record> element contains a set of mandatory elements. Other optional elements may appear, depending on the audit record type.

The following elements are mandatory in every <audit_record> element:

<NAME>

A string representing the type of instruction that generated the audit event, such as a command that the server received from a client.

Example:

```
<NAME>Query</NAME>
```

Some common <NAME> values:

```
Audit When auditing starts, which may be server startup time

Connect When a client connects, also known as logging in

Query An SQL statement (executed directly)

Prepare Preparation of an SQL statement; usually followed by Execute

Execute Execution of an SQL statement; usually follows Prepare

Shutdown Server shutdown

Quit When a client disconnects

NoAudit Auditing has been turned off
```

The possible values are Audit, Binlog Dump, Change user, Close stmt, Connect Out, Connect, Create DB, Daemon, Debug, Delayed insert, Drop DB, Execute, Fetch, Field List, Init DB, Kill, Long Data, NoAudit, Ping, Prepare, Processlist, Query, Quit, Refresh, Register Slave, Reset stmt, Set option, Shutdown, Sleep, Statistics, Table Dump, Time.

With the exception of Audit and NoAudit, these values correspond to the COM_xxx command values listed in the mysql_com.h header file. For example, Create DB and Shutdown correspond to COM_CREATE_DB and COM_SHUTDOWN, respectively.

• <RECORD_ID>

A unique identifier for the audit record. The value is composed from a sequence number and timestamp, in the format SEQ_TIMESTAMP. The sequence number is initialized to the size of the audit log file at the

time the audit log plugin opens it and increments by 1 for each record logged. The timestamp is a UTC value in yyyy-mm-ddThh:mm:ss format indicating the time when the audit log plugin opened the file.

Example:

```
<RECORD_ID>28743_2013-09-18T21:03:24</recORD_ID>
```

<TIMESTAMP>

The date and time that the audit event was generated. For example, the event corresponding to execution of an SQL statement received from a client has a <TIMESTAMP> value occurring after the statement finishes, not when it is received. The value has the format yyyy-mm-ddThh:mm:ss UTC (with T, no decimals). The format includes a time zone specifier at the end. The time zone is always UTC.

Example:

```
<TIMESTAMP>2013-09-17T15:03:49 UTC</TIMESTAMP>
```

The following elements are optional in <AUDIT_RECORD> elements. Many of them occur only with specific <NAME> values.

• <COMMAND_CLASS>

A string that indicates the type of action performed.

Example:

```
<COMMAND_CLASS>drop_table</COMMAND_CLASS>
```

The values come from the com_status_vars array in the sql/mysqld.cc file in a MySQL source distribution. They correspond to the status variables displayed by this statement:

```
SHOW STATUS LIKE 'Com%';
```

• <CONNECTION_ID>

An unsigned integer representing the client connection identifier. This is the same as the CONNECTION_ID() function value within the session.

Example:

```
<CONNECTION_ID>127</CONNECTION_ID>
```

• <DB>

A string representing the default database name. This element appears only if the <NAME> value is Connect or Change user.

• <HOST>

A string representing the client host name. This element appears only if the <NAME> value is Connect, Change user, Or Query.

Example:

<HOST>localhost</HOST>

• <IP>

A string representing the client IP address. This element appears only if the <NAME> value is Connect, Change user, or Query.

Example:

<IP>127.0.0.1</IP>

• <MYSOL VERSION>

A string representing the MySQL server version. This is the same as the value of the VERSION() function or version system variable. This element appears only if the <NAME> value is Audit.

Example:

<MYSQL_VERSION>5.7.1-m11-log</mysQL_VERSION>

• <OS_LOGIN>

A string representing the external user name used during the authentication process, as set by the plugin used to authenticate the client. With native (built-in) MySQL authentication, or if the plugin does not set the value, this variable is NULL. The value is the same as that of the external_user system variable. See Section 5.8, "Proxy Users".

This element appears only if the <NAME > value is Connect, Change user, or Query.

<OS_VERSION>

A string representing the operating system on which the server was built or is running. This element appears only if the <name> value is Audit.

Example:

<OS_VERSION>x86_64-Linux/OS_VERSION>

• <PRIV USER>

A string representing the user that the server authenticated the client as. This is the user name that the server uses for privilege checking, and may differ from the <USER> value. This element appears only if the <NAME> value is Connect or Change user.

• <PROXY_USER>

A string representing the proxy user. The value is empty if user proxying is not in effect. This element appears only if the <NAME> value is Connect or Change user.

• <SERVER ID>

An unsigned integer representing the server ID. This is the same as the value of the server_id system variable. This element appears only if the <NAME> value is Audit or NoAudit.

Example:

```
<SERVER_ID>1</SERVER_ID>
```

• <SQLTEXT>

A string representing the text of an SQL statement. The value can be empty. Long values may be truncated. This element appears only if the <NAME> value is Query or Execute.

The string, like the audit log file itself, is written using UTF-8 (up to 4 bytes per character), so the value may be the result of conversion. For example, the original statement might have been received from the client as an SJIS string.

Example:

```
<SQLTEXT>DELETE FROM t1</SQLTEXT>
```

• <STARTUP_OPTIONS>

A string representing the options that were given on the command line or in option files when the MySQL server was started. This element appears only if the <NAME> value is Audit.

Example:

```
<STARTUP_OPTIONS>/usr/local/mysql/bin/mysqld
--port=3306 --log-output=FILE</STARTUP_OPTIONS>
```

• <STATUS>

An unsigned integer representing the command status: 0 for success, nonzero if an error occurred. This is the same as the value of the <code>mysql_errno()</code> C API function.

The audit log does not contain the SQLSTATE value or error message. To see the associations between error codes, SQLSTATE values, and messages, see Server Error Codes and Messages.

Warnings are not logged.

See the description for <STATUS_CODE> for information about how it differs from <STATUS>.

Example:

```
<STATUS>1051</STATUS>
```

• <STATUS CODE>

An unsigned integer representing the command status: 0 for success, 1 if an error occurred.

The STATUS_CODE value differs from the STATUS value: STATUS_CODE is 0 for success and 1 for error, which is compatible with the EZ_collector consumer for Audit Vault. STATUS is the value of the <code>mysql_erroo()</code> C API function. This is 0 for success and nonzero for error, and thus is not necessarily 1 for error.

Example:

```
<STATUS_CODE>0</STATUS_CODE>
```

• <USER>

A string representing the user name sent by the client. This may differ from the <PRIV_USER> value. This element appears only if the <NAME> value is Connect, Change user, or Query.

Example:

```
<USER>root[root] @ localhost [127.0.0.1]</USER>
```

• <VERSION>

An unsigned integer representing the version of the audit log file format. This element appears only if the <NAME> value is Audit.

Example:

```
<VERSION>1</VERSION>
```

Old Audit Log File Format

Every <audit_record> element contains a set of mandatory attributes. Other optional attributes may appear depending on the audit record type.

The following attributes are mandatory in every <audit_record> element:

NAME

A string representing the type of instruction that generated the audit event, such as a command that the server received from a client.

Example: NAME="Query"

Some common NAME values:

```
"Audit" When auditing starts, which may be server startup time
"Connect" When a client connects, also known as logging in
"Query" An SQL statement (executed directly)
"Prepare" Preparation of an SQL statement; usually followed by Execute
"Execute" Execution of an SQL statement; usually follows Prepare
"Shutdown" Server shutdown
"Quit" When a client disconnects
"NoAudit" Auditing has been turned off
```

The possible values are "Audit", "Binlog Dump", "Change user", "Close stmt", "Connect Out", "Connect", "Create DB", "Daemon", "Debug", "Delayed insert", "Drop DB", "Execute", "Fetch", "Field List", "Init DB", "Kill", "Long Data", "NoAudit", "Ping", "Prepare", "Processlist", "Query", "Quit", "Refresh", "Register Slave", "Reset stmt", "Set option", "Shutdown", "Sleep", "Statistics", "Table Dump", "Time".

With the exception of "Audit" and "NoAudit", these values correspond to the COM_xxx command values listed in the mysql_com.h header file. For example, "Create DB" and "Shutdown" correspond to COM_CREATE_DB and COM_SHUTDOWN, respectively.

• TIMESTAMP

The date and time that the audit event was generated. For example, the event corresponding to execution of an SQL statement received from a client has a TIMESTAMP value occurring after the

statement finishes, not when it is received. The value is UTC, in the format yyyy-mm-ddThh: mm:ss (with T, no decimals).

```
Example: TIMESTAMP="2012-08-09T12:55:16"
```

The following attributes are optional in <audit_record> elements. Many of them occur only for elements with specific values of the NAME attribute.

• CONNECTION ID

An unsigned integer representing the client connection identifier. This is the same as the CONNECTION_ID() function value within the session.

```
Example: CONNECTION_ID="127"
```

• DB

A string representing the default database name. This attribute appears only if the NAME value is "Connect" or "Change user".

• HOST

A string representing the client host name. This attribute appears only if the NAME value is "Connect" or "Change user".

```
Example: HOST="localhost"
```

• IP

A string representing the client IP address. This attribute appears only if the NAME value is "Connect" or "Change user".

```
Example: IP="127.0.0.1"
```

• MYSQL_VERSION

A string representing the MySQL server version. This is the same as the value of the VERSION() function or version system variable. This attribute appears only if the NAME value is "Audit".

```
Example: MYSQL_VERSION="5.6.11-log"
```

• OS_LOGIN

A string representing the external user (empty if none). The value may differ from USER, for example, if the server authenticates the client using an external authentication method. This attribute appears only if the NAME value is "Connect" or "Change user".

• OS_VERSION

A string representing the operating system on which the server was built or is running. This attribute appears only if the NAME value is "Audit".

```
Example: OS_VERSION="x86_64-Linux"
```

• PRIV USER

A string representing the user that the server authenticated the client as. This is the user name that the server uses for privilege checking, and may be different from the USER value. This attribute appears only if the NAME value is "Connect" or "Change user".

• PROXY_USER

A string representing the proxy user. The value is empty if user proxying is not in effect. This attribute appears only if the NAME value is "Connect" or "Change user".

• SERVER_ID

An unsigned integer representing the server ID. This is the same as the value of the server_id system variable. This attribute appears only if the NAME value is "Audit" or "NoAudit".

Example: SERVER ID="1"

• SQLTEXT

A string representing the text of an SQL statement. The value can be empty. Long values may be truncated. This attribute appears only if the NAME value is "Query" or "Execute".

The string, like the audit log file itself, is written using UTF-8 (up to 4 bytes per character), so the value may be the result of conversion. For example, the original statement might have been received from the client as an SJIS string.

Example: SQLTEXT="DELETE FROM t1"

• STARTUP_OPTIONS

A string representing the options that were given on the command line or in option files when the MySQL server was started. This attribute appears only if the NAME value is "Audit".

Example: STARTUP_OPTIONS="--port=3306 --log-output=FILE"

• STATUS

An unsigned integer representing the command status: 0 for success, nonzero if an error occurred. This is the same as the value of the $mysql_{errno}()$ C API function.

The audit log does not contain the SQLSTATE value or error message. To see the associations between error codes, SQLSTATE values, and messages, see Server Error Codes and Messages.

Warnings are not logged.

Example: STATUS="1051"

• USER

A string representing the user name sent by the client. This may be different from the PRIV_USER value. This attribute appears only if the NAME value is "Connect" or "Change user".

• VERSION

An unsigned integer representing the version of the audit log file format. This attribute appears only if the NAME value is "Audit".

Example: VERSION="1"

6.3.4 Audit Log Logging Control

This section describes how the audit_log plugin performs logging and the system variables that control how logging occurs. It assumes familiarity with the log file format described in Section 6.3.3, "The Audit Log File".

The audit_log plugin can also control whether audited events are written to the audit log file based on the account from which events originate or event status. See Section 6.3.5, "Audit Log Filtering".

When the audit log plugin opens its log file, it checks whether the XML declaration and opening AUDIT> root element tag must be written and writes them if so. When the audit log plugin terminates, it writes a closing AUDIT> tag to the file.

If the log file exists at open time, the plugin checks whether the file ends with an </AUDIT> tag and truncates it if so before writing any <AUDIT_RECORD> elements. If the log file exists but does not end with </AUDIT> or the </AUDIT> tag cannot be truncated, the plugin considers the file malformed and fails to initialize. This can occur if the server crashes or is killed with the audit log plugin running. No logging occurs until the problem is rectified. Check the error log for diagnostic information:

```
[ERROR] Plugin 'audit_log' init function returned error.
```

To deal with this problem, either remove or rename the malformed log file and restart the server.

The MySQL server calls the audit log plugin to write an <audit log logical contents are contents are logged, not statements within stored programs such as triggers or stored procedures. Contents of files referenced by statements such as LOAD DATA INFILE are not logged.

To permit control over how logging occurs, the audit_log plugin provides several system variables, described following. For more information, see Section 6.3.6.2, "Audit Log Options and System Variables".

Audit Log File Naming

To control the audit log file name, set the audit_log_file system variable at server startup. By default, the name is audit.log in the server data directory. For security reasons, the audit log file should be written to a directory accessible only to the MySQL server and users with a legitimate reason to view the log.

Audit Logging Strategy

The audit log plugin can use any of several strategies for log writes. To specify a strategy, set the audit_log_strategy system variable at server startup. By default, the strategy value is ASYNCHRONOUS and the plugin logs asynchronously to a buffer, waiting if the buffer is full. It's possible to tell the plugin not to wait (PERFORMANCE) or to log synchronously, either using file system caching (SEMISYNCHRONOUS) or forcing output with a sync() call after each write request (SYNCHRONOUS).

Asynchronous logging strategy has these characteristics:

- · Minimal impact on server performance and scalability.
- Blocking of threads that generate audit events for the shortest possible time; that is, time to allocate the buffer plus time to copy the event to the buffer.
- Output goes to the buffer. A separate thread handles writes from the buffer to the log file.

A disadvantage of PERFORMANCE strategy is that it drops events when the buffer is full. For a heavily loaded server, it is more likely that the audit log will be missing events.

With asynchronous logging, the integrity of the log file may be compromised if a problem occurs during a write to the file or if the plugin does not shut down cleanly (for example, in the event that the server host crashes). To reduce this risk, set audit_log_strategy to use synchronous logging. Regardless of strategy, logging occurs on a best-effort basis, with no guarantee of consistency.

If the file system to which the audit log is being written fills up, a "disk full" error is written to the error log. Audit logging continues until the audit log buffer is full. If free disk space has not been made available by the time the buffer fills, client sessions will hang, and stopping the server at the time of client sessions hanging will result in audit log corruption. To avoid this if client sessions are hung, ensure that free space is available on the audit logging file system before stopping the server.

Audit Log Space Management

The audit log plugin provides several system variables that enable you to manage the space used by its log files:

- audit_log_buffer_size: Set this variable at server startup to set the size of the buffer for asynchronous logging. The plugin uses a single buffer, which it allocates when it initializes and removes when it terminates. The plugin allocates this buffer only if logging is asynchronous.
- audit_log_rotate_on_size, audit_log_flush: These variables permit audit log file rotation and flushing. The audit log file has the potential to grow very large and consume a lot of disk space. To manage the space used, either enable automatic log rotation, or manually rename the audit file and flush the log to open a new file. The renamed file can be removed or backed up as desired.

By default, audit_log_rotate_on_size=0 and there is no log rotation. In this case, the audit log plugin closes and reopens the log file when the audit_log_flush value changes from disabled to enabled. Log file renaming must be done externally to the server. Suppose that you want to maintain the three most recent log files, which cycle through the names audit.log.1 through audit.log.3. On Unix, perform rotation manually like this:

1. From the command line, rename the current log files:

```
mv audit.log.2 audit.log.3
mv audit.log.1 audit.log.2
mv audit.log audit.log.1
```

At this point, the plugin is still writing to the current log file, which has been renamed to audit.log.1.

Connect to the server and flush the log file so the plugin closes it and reopens a new audit.log file:

```
SET GLOBAL audit_log_flush = ON;
```

If audit_log_rotate_on_size is greater than 0, setting audit_log_flush has no effect. In this case, the audit log plugin closes and reopens its log file whenever a write to the file causes its size to exceed the audit_log_rotate_on_size value. The plugin renames the original file to have a timestamp extension. For example, audit.log might be renamed to audit.log.13440033615657730. The last 7 digits are a fractional second part. The first 10 digits are a Unix timestamp value that can be interpreted using the FROM UNIXTIME() function:

6.3.5 Audit Log Filtering

The audit_log plugin can filter audited events. This enables you to control whether audited events are written to the audit log file based on the account from which events originate or event status. Status filtering occurs separately for connection events and statement events.

Event Filtering by Account

As of MySQL 5.6.20, to filter audited events based on the originating account, set one of these system variables at server startup or runtime:

- audit_log_include_accounts: The accounts to include in audit logging. If this variable is set, only these accounts are audited.
- audit_log_exclude_accounts: The accounts to exclude from audit logging. If this variable is set, all but these accounts are audited.

The value for either variable can be NULL or a string containing one or more comma-separated account names, each in <code>user_name@host_name</code> format. By default, both variables are <code>NULL</code>, in which case, no account filtering is done and auditing occurs for all accounts.

Modifications to audit_log_include_accounts or audit_log_exclude_accounts affect only connections created subsequent to the modification, not existing connections.

Example: To enable audit logging only for the user1 and user2 local host account accounts, set the audit_log_include_accounts system variable like this:

```
SET GLOBAL audit_log_include_accounts = 'user1@localhost,user2@localhost';
```

Only one of $audit_log_include_accounts$ or $audit_log_exclude_accounts$ can be non-NULL at a time:

- If you set audit_log_include_accounts, the server sets audit_log_exclude_accounts to NULL.
- If you attempt to set audit_log_exclude_accounts, an error occurs unless audit_log_include_accounts is NULL. In this case, you must first clear audit_log_include_accounts by setting it to NULL.

```
-- This sets audit_log_exclude_accounts to NULL

SET GLOBAL audit_log_include_accounts = value;

-- This fails because audit_log_include_accounts is not NULL

SET GLOBAL audit_log_exclude_accounts = value;

-- To set audit_log_exclude_accounts, first set

-- audit_log_include_accounts to NULL

SET GLOBAL audit_log_include_accounts = NULL;

SET GLOBAL audit_log_exclude_accounts = value;
```

If you inspect the value of either variable, be aware that SHOW VARIABLES displays NULL as an empty string. To avoid this, use SELECT instead:

If a user name or host name requires quoting because it contains a comma, space, or other special character, quote it using single quotes. If the variable value itself is quoted with single quotes, double each inner single quote or escape it with a backslash. The following statements each enable audit logging for the local root account and are equivalent, even though the quoting styles differ:

```
SET GLOBAL audit_log_include_accounts = 'root@localhost';
SET GLOBAL audit_log_include_accounts = '''root''@''localhost''';
SET GLOBAL audit_log_include_accounts = '\'root\'@\'localhost\'';
SET GLOBAL audit_log_include_accounts = "'root'@'localhost'";
```

The last statement will not work if the ANSI_QUOTES SQL mode is enabled because in that mode double quotes signify identifier quoting, not string quoting.

Event Filtering by Status

As of MySQL 5.6.20, to filter audited events based on status, set these system variables at server startup or runtime:

- audit_log_connection_policy: Logging policy for connection events
- audit_log_statement_policy: Logging policy for statement events

Each variable takes a value of ALL (log all associated events; this is the default), ERRORS (log only failed events), or NONE (do not log events). For example, to log all statement events but only failed connection events, use these settings:

```
SET GLOBAL audit_log_statement_policy = ALL;
SET GLOBAL audit_log_connection_policy = ERRORS;
```

Before MySQL 5.6.20, audit_log_connection_policy and audit_log_statement_policy are not available. Instead, use audit_log_policy at server startup or runtime. It takes a value of ALL (log all events; this is the default), LOGINS (log connection events), QUERIES (log statement events), or NONE (do not log events). For any of those values, the audit log plugin logs all selected events without distinction as to success or failure.

As of MySQL 5.6.20, audit_log_policy is still available but can be set only at server startup. At runtime, it is a read-only variable. Its use at startup works as follows:

- If you do not set audit_log_policy or set it to its default of ALL, any explicit settings for audit_log_connection_policy or audit_log_statement_policy apply as specified. If not specified, they default to ALL.
- If you set audit_log_policy to a non-ALL value, that value takes precedence over and is used to set audit_log_connection_policy and audit_log_statement_policy, as indicated in the following table. If you also set either of those variables to a value other than their default of ALL, the server writes a message to the error log to indicate that their values are being overridden.

Startup audit_log_policy Value	Resulting audit_log_connection_policy Value	Resulting audit_log_statement_policy Value
LOGINS	ALL	NONE
QUERIES	NONE	ALL
NONE	NONE	NONE

Event Filtering Reporting

To check the effect of filtering, you can inspect the values of these status variables:

- Audit_log_events: The number of events handled by the audit log plugin, whether or not they were written to the log based on filtering policy.
- Audit_log_events_filtered: The number of events handled by the audit log plugin that were filtered (not written to the log) based on filtering policy.
- Audit_log_events_written: The number of events written to the audit log.

These variables are available as of MySQL 5.6.20.

6.3.6 Audit Log Reference

The following discussion serves as a reference to these MySQL Enterprise Audit components:

- · Audit log system variables
- Audit log status variables

6.3.6.1 Audit Log Option and Variable Reference

Table 6.9 Audit Log Option/Variable Reference

Name	Cmd-Line	Option File	System Var	Status Var	Var Scope	Dynamic
audit-log	Yes	Yes				
audit_log_buffer_siz	≱6es	Yes	Yes		Global	No
audit_log_connection	ome_spolicy	Yes	Yes		Global	Yes
audit_log_current_s	session		Yes		Both	No
Audit_log_current_s	size			Yes	Global	No
Audit_log_event_m	ax_drop_size			Yes	Global	No
Audit_log_events				Yes	Global	No
Audit_log_events_fi	iltered			Yes	Global	No
Audit_log_events_log	ost			Yes	Global	No
Audit_log_events_v	vritten			Yes	Global	No
audit_log_exclude_	alesounts	Yes	Yes		Global	Yes
audit_log_file	Yes	Yes	Yes		Global	No
audit_log_flush			Yes		Global	Yes
audit_log_format	Yes	Yes	Yes		Global	No
audit_log_include_a	a óes unts	Yes	Yes		Global	Yes

Name	Cmd-Line	Option File	System Var	Status Var	Var Scope	Dynamic
audit_log_policy	Yes	Yes	Yes		Global	Varies
audit_log_rotate_o	n <u>Y</u> esze	Yes	Yes		Global	Yes
audit_log_stateme	n Y_eps olicy	Yes	Yes		Global	Yes
audit_log_strategy	Yes	Yes	Yes		Global	No
Audit_log_total_siz	е			Yes	Global	No
Audit_log_write_wa	aits			Yes	Global	No

6.3.6.2 Audit Log Options and System Variables

This section describes the command options and system variables that control operation of MySQL Enterprise Audit. If values specified at startup time are incorrect, the audit_log plugin may fail to initialize properly and the server does not load it. In this case, the server may also produce error messages for other audit log settings because it will not recognize them.

To control the activation of the audit_log plugin, use this option:

--audit-log[=value]

Introduced	5.6.10		
Command-Line Format	audit-log[=value]		
Permitted Values	Type enumeration		
	Default	ON	
	Valid	ON	
	Values	OFF	
		FORCE	
		FORCE_PLUS_PERMANENT	

This option controls how the server loads the audit_log plugin at startup. It is available only if the plugin has been previously registered with INSTALL PLUGIN or is loaded with --plugin-load. See Section 6.3.1, "Installing MySQL Enterprise Audit".

The option value should be one of those available for plugin-loading options, as described in Installing and Uninstalling Plugins. For example, --audit-log=FORCE_PLUS_PERMANENT tells the server to load the plugin at startup and prevents it from being removed while the server is running.

If the audit_log plugin is enabled, it exposes several system variables that permit control over logging:

audit_log_statement_policy	ALL
audit_log_strategy	ASYNCHRONOUS
+	++

You can set any of these variables at server startup, and some of them at runtime.

• audit_log_buffer_size

Introduced	5.6.10			
Command-Line Format	audit	audit_log_buffer_size=value		
System Variable	Name	audit_log_buffer_size		
	Variable Scope	Global		
	Dynamic Variable			
Permitted Values (32-bit	Туре	integer		
platforms)	Default	1048576		
	Min Value	4096		
	Max Value	4294967295		
Permitted Values (64-bit	Туре	integer		
platforms)	Default	1048576		
	Min Value	4096		
	Max Value	18446744073709547520		

When the audit log plugin writes events to the log asynchronously, it uses a buffer to store event contents prior to writing them. This variable controls the size of that buffer, in bytes. The server adjusts the value to a multiple of 4096. The plugin uses a single buffer, which it allocates when it initializes and removes when it terminates. The plugin allocates this buffer only if logging is asynchronous.

audit_log_connection_policy

Introduced	5.6.20		
Command-Line Format	audit_log_connection_policy=value		
System Variable	Name audit_log_connection_policy		
	Variable Scope	Global	
	Dynamic Variable		
Permitted Values	Туре	enumeration	
	Default	ALL	
	Valid	ALL	
	Values	ERRORS	
		NONE	

The policy controlling how the audit log plugin writes connection events to its log file. The following table shows the permitted values.

Value	Description
ALL	Log all connection events
ERRORS	Log only failed connection events
NONE	Do not log connection events

Note

At server startup, any explicit value given for audit_log_connection_policy may be overridden if audit_log_policy is also specified, as described in Section 6.3.4, "Audit Log Logging Control".

• audit_log_current_session

Introduced	5.6.20	
System Variable	Name	audit_log_current_session
	Variable Scope	Global, Session
	Dynamic Variable	
Permitted Values	Туре	boolean
	Default	depends on filtering policy

Whether audit logging is enabled for the current session. The session value of this variable is read only. It is set when the session begins based on the values of the audit_log_include_accounts and audit_log_exclude_accounts system variables. The audit log plugin uses the session value to determine whether to audit events for the session. (There is a global value, but the plugin does not use it.)

audit_log_exclude_accounts

Introduced	5.6.20	5.6.20		
Command-Line Format	audit	audit_log_exclude_accounts=value		
System Variable	Name	Name audit_log_exclude_accounts		
	Variable Scope	Global		
	Dynamic Variable			
Permitted Values	Туре	string		
	Default	NULL		

The accounts for which events should not be logged. The value should be NULL or a string containing a list of one or more comma-separated account names. For more information, see Section 6.3.4, "Audit Log Logging Control".

Modifications to audit_log_exclude_accounts affect only connections created subsequent to the modification, not existing connections.

audit_log_file

Introduced	5.6.10	5.6.10		
Command-Line Format	audit	audit_log_file=file_name		
System Variable	Name	audit_log_file		
	Variable Scope	Global		
	Dynamic Variable			
Permitted Values	Туре	file name		
	Default	audit.log		

The name of the file to which the audit log plugin writes events. The default value is audit.log. If the value of audit_log_file is a relative path name, the server interprets it relative to the data directory. If the value is a full path name, the server uses the value as is. A full path name may be useful if it is desirable to locate audit files on a separate file system or directory. For security reasons, the audit log file should be written to a directory accessible only to the MySQL server and users with a legitimate reason to view the log. For more information, see Section 6.3.4, "Audit Log Logging Control".

audit_log_flush

Introduced	5.6.10	
System Variable	Name	audit_log_flush
	Variable Scope	Global
	Dynamic Variable	
Permitted Values	Туре	boolean
	Default	OFF

When this variable is set to enabled (1 or ON), the audit log plugin closes and reopens its log file to flush it. (The value remains OFF so that you need not disable it explicitly before enabling it again to perform another flush.) Enabling this variable has no effect unless audit_log_rotate_on_size is 0. For more information, see Section 6.3.4, "Audit Log Logging Control".

audit_log_format

Introduced	5.6.14	
Command-Line Format	audit_log_format=value	
System Variable	Name audit_log_format	
	Variable Scope	Global
	Dynamic Variable	

Permitted Values (>=	Туре	enumeration
5.6.14)	Default	OLD
	Valid	OLD
	Values	NEW

The audit log file format. Permitted values are OLD and NEW (default OLD). For details about each format, see Section 6.3.3, "The Audit Log File".

If you change the value of audit_log_format, use this procedure to avoid writing log entries in one format to an existing log file that contains entries in a different format:

- 1. Stop the server.
- 2. Rename the current audit log file manually.
- 3. Restart the server with the new value of audit_log_format. The audit log plugin will create a new log file, which will contain log entries in the selected format.
- audit_log_include_accounts

Introduced	5.6.20	
Command-Line Format	audit_log_include_accounts=value	
System Variable	Name audit_log_include_accounts	
	Variable Scope	Global
	Dynamic Variable	
Permitted Values	Туре	string
	Default	NULL

The accounts for which events should be logged. The value should be NULL or a string containing a list of one or more comma-separated account names. For more information, see Section 6.3.4, "Audit Log Logging Control".

Modifications to audit_log_include_accounts affect only connections created subsequent to the modification, not existing connections.

audit_log_policy

Introduced	5.6.10		
Command-Line Format	audit	audit_log_policy=value	
System Variable (<=	Name	audit_log_policy	
5.6.19)	Variable	Global	
	Scope		
	Dynamic Variable	eYes	
System Variable (>=	Name	audit_log_policy	
5.6.20)	Variable	Global	
	Scope	4.2	

	Dynamic Variable	
Permitted Values	Туре	enumeration
	Default	ALL
	Valid	ALL
	Values	LOGINS
		QUERIES
		NONE

The policy controlling how the audit log plugin writes events to its log file. The following table shows the permitted values.

Value	Description
ALL	Log all events
LOGINS	Log only login events
QUERIES	Log only query events
NONE	Log nothing (disable the audit stream)

As of MySQL 5.6.20, audit_log_policy can be set only at server startup. At runtime, it is a read-only variable. This is due to the introduction of two other system variables, audit_log_connection_policy and audit_log_statement_policy, that provide finer control over logging policy and that can be set either at startup or at runtime. If you continue to use audit_log_policy at startup instead of the other two variables, the server uses its value to set those variables. For more information about the policy variables and their interaction, see Section 6.3.4, "Audit Log Logging Control".

Before MySQL 5.6.20, the audit_log_connection_policy and audit_log_statement_policy system variables do not exist. audit_log_policy is the only policy control variable and it can be set at server startup or runtime.

• audit_log_rotate_on_size

Introduced	5.6.10		
Command-Line Format	audit	audit_log_rotate_on_size=N	
System Variable	Name audit_log_rotate_on_size		
	Variable Scope	Global	
	Dynamic Variable		
Permitted Values	Туре	integer	
	Default	0	

If the audit_log_rotate_on_size value is greater than 0, the audit log plugin closes and reopens its log file if a write to the file causes its size to exceed this value. The original file is renamed to have a timestamp extension.

If the audit_log_rotate_on_size value is 0, the plugin does not close and reopen its log based on size. Instead, use audit_log_flush to close and reopen the log on demand. In this case, rename the file externally to the server before flushing it.

For more information about audit log file rotation and timestamp interpretation, see Section 6.3.4, "Audit Log Logging Control".

If you set this variable to a value that is not a multiple of 4096, it is truncated to the nearest multiple. (Thus, setting it to a value less than 4096 has the effect of setting it to 0 and no rotation occurs.)

• audit_log_statement_policy

Introduced	5.6.20	
Command-Line Format	audit	
System Variable	Name	audit_log_statement_policy
	Variable Scope	Global
	Dynamic Variable	
Permitted Values	Туре	enumeration
	Default	ALL
	Valid	ALL
	Values	ERRORS
		NONE

The policy controlling how the audit log plugin writes statement events to its log file. The following table shows the permitted values.

Value	Description
ALL	Log all statement events
ERRORS	Log only failed statement events
NONE	Do not log statement events

Note

At server startup, any explicit value given for $audit_log_statement_policy$ may be overridden if $audit_log_policy$ is also specified, as described in Section 6.3.4, "Audit Log Logging Control".

• audit_log_strategy

Introduced	5.6.10	
Command-Line Format	audit_log_strategy=value	
System Variable	Name audit_log_strategy	
	Variable Scope	Global
	Dynamic Variable	

Permitted Values	Туре	enumeration
	Default	ASYNCHRONOUS
	Valid	ASYNCHRONOUS
	Values	PERFORMANCE
		SEMISYNCHRONOUS
		SYNCHRONOUS

The logging method used by the audit log plugin. The following table describes the permitted values.

Table 6.10 Audit Log Strategies

Value	Meaning
ASYNCHRONOUS	Log asynchronously, wait for space in output buffer
PERFORMANCE	Log asynchronously, drop request if insufficient space in output buffer
SEMISYNCHRONOUS	Log synchronously, permit caching by operating system
SYNCHRONOUS	Log synchronously, call sync() after each request

6.3.6.3 Audit Log Plugin Status Variables

If the audit_log plugin is enabled, it exposes several status variables that provide operational information.

• Audit_log_current_size

The size of the current audit log file. The value increases when an event is written to the log and is reset to 0 when the log is rotated.

• Audit_log_event_max_drop_size

The size of the largest dropped event in performance logging mode. For a description of logging modes, see Section 6.3.4, "Audit Log Logging Control".

• Audit_log_events

The number of events handled by the audit log plugin, whether or not they were written to the log based on filtering policy (see Section 6.3.4, "Audit Log Logging Control").

Audit_log_events_filtered

The number of events handled by the audit log plugin that were filtered (not written to the log) based on filtering policy (see Section 6.3.4, "Audit Log Logging Control").

Audit_log_events_lost

The number of events lost in performance logging mode because an event was larger than than the available audit log buffer space. This value may be useful for assessing how to set audit_log_buffer_size to size the buffer for performance mode. For a description of logging modes, see Section 6.3.4, "Audit Log Logging Control".

• Audit_log_events_written

The number of events written to the audit log.

• Audit_log_total_size

The total size of events written to all audit log files. Unlike Audit_log_current_size, the value of Audit log total size increases even when the log is rotated.

Audit_log_write_waits

The number of times an event had to wait for space in the audit log buffer in asynchronous logging mode. For a description of logging modes, see Section 6.3.4, "Audit Log Logging Control".

6.3.7 Audit Log Restrictions

MySQL Enterprise Audit is subject to these general restrictions:

- Only SQL statements are logged. Changes made by no-SQL APIs, such as memcached, Node.JS, and the NDB API, are not logged.
- Only top-level statements are logged, not statements within stored programs such as triggers or stored procedures.
- Contents of files referenced by statements such as LOAD DATA INFILE are not logged.

MySQL Cluster. It is possible to use MySQL Enterprise Audit with MySQL Cluster, subject to the following conditions:

- All changes to be logged must be done using the SQL interface. Changes using no-SQL interfaces, such
 as those provided by the NDB API, memcached, or ClusterJ, are not logged.
- The plugin must be installed on each MySQL server that is used to execute SQL on the cluster.
- Audit plugin data must be aggregated amongst all MySQL servers used with the cluster. This
 aggregation is the responsibility of the application or user.

6.4 MySQL Enterprise Firewall

Note

MySQL Enterprise Firewall is an extension included in MySQL Enterprise Edition, a commercial product. To learn more about commercial products, see http://www.mysql.com/products/.

As of MySQL 5.6.24, MySQL Enterprise Edition includes MySQL Enterprise Firewall, an application-level firewall that enables database administrators to permit or deny SQL statement execution based on matching against whitelists of accepted statement patterns. This helps harden MySQL Server against attacks such as SQL injection or attempts to exploit applications by using them outside of their legitimate query workload characteristics.

Each MySQL account registered with the firewall has its own statement whitelist, enabling protection to be tailored per account. For a given account, the firewall can operate in recording, protecting, or detecting mode, for training in the accepted statement patterns, active protection against unacceptable statements, or passive detection of unacceptable statements. The diagram illustrates how the firewall processes incoming statements in each mode.




Figure 6.1 MySQL Enterprise Firewall Operation

The following sections describe the components of MySQL Enterprise Firewall, discuss how to install and use it, and provide reference information for its components.

6.4.1 MySQL Enterprise Firewall Components

MySQL Enterprise Firewall is based on a plugin library that implements these components:

- A server-side plugin named MYSQL_FIREWALL examines SQL statements before they execute and, based on its in-memory cache, renders a decision whether to execute or reject each statement.
- Server-side plugins named MYSQL_FIREWALL_USERS and MYSQL_FIREWALL_WHITELIST implement INFORMATION_SCHEMA tables that provide views into the firewall data cache.
- System tables named firewall_users and firewall_whitelist in the mysql database provide persistent storage of firewall data.
- Stored procedures named <code>sp_set_firewall_mode()</code> and <code>sp_reload_firewall_rules()</code> perform tasks such as registering MySQL accounts with the firewall, establishing their operational mode, and managing transfer of firewall data between the cache and the underlying system tables.
- A set of user-defined functions provides an SQL-level API for lower-level tasks such as synchronizing the cache with the underlying system tables.
- System variables enable firewall configuration and status variables provide runtime operational information.

6.4.2 Installing or Uninstalling MySQL Enterprise Firewall

MySQL Enterprise Firewall installation is a one-time operation that installs the components described in Section 6.4.1, "MySQL Enterprise Firewall Components". Installation can be performed using a graphical interface or manually:

- On Windows, MySQL Installer includes an option to enable MySQL Enterprise Firewall for you.
- MySQL Workbench 6.3.4 or higher can install MySQL Enterprise Firewall, enable or disable an installed firewall, or uninstall the firewall.
- Manual MySQL Enterprise Firewall installation involves running a script located in the share directory of your MySQL installation.

Note

If installed, MySQL Enterprise Firewall involves some minimal overhead even when disabled. To avoid this overhead, do not install the firewall unless you plan to use it.

Note

MySQL Enterprise Firewall does not work together with the query cache. If the query cache is enabled, disable it before installing the firewall (see Query Cache Configuration).

For usage instructions, see Section 6.4.3, "Using MySQL Enterprise Firewall". For reference information, see Section 6.4.4, "MySQL Enterprise Firewall Reference".

Installing MySQL Enterprise Firewall

If MySQL Enterprise Firewall is already installed from an older version of MySQL, uninstall it using the instructions given later in this section and then restart your server before installing the current version. In this case, it is also necessary to register your configuration again.

On Windows, you can use MySQL Installer to install MySQL Enterprise Firewall, as shown in Figure 6.2, "MySQL Enterprise Firewall Installation on Windows". Check the **Enable Enterprise Firewall** checkbox. (**Open Firewall port for network access** has a different purpose. It refers to Windows Firewall and controls whether Windows blocks the TCP/IP port on which the MySQL server listens for client connections.)

D MySQL Installer MySQL: Installer Type and Networking MySQL Server 5.6.25 Server Configuration Type Choose the correct server configuration type for this MySQL Server installation. This setting will define how much system resources are assigned to the MySQL Server instance. Type and Networking Config Type: Development Machine Accounts and Roles Connectivity Use the following controls to select how you would like to connect to this server. Windows Service ▼ TCP/IP Port Number: Apply Server Configuration ✓ Open Firewall port for network access ■ Named Pipe Pipe Name: MYSQL Shared Memory Memory Name: MYSQL Advanced Configuration Select the checkbox below to get additional configuration page where you can set advanced options for this server instance. Show Advanced Options MySQL Enterprise Firewall Select the checkbox below to enable the Enterprise Firewall, a security whitelist that offers protection from cyber attacks. Additional post installation configuration is necessary. ✓ Enable Enterprise Firewall Click here to view the online documentation. Next > Cancel

Figure 6.2 MySQL Enterprise Firewall Installation on Windows

To install MySQL Enterprise Firewall using MySQL Workbench 6.3.4 or higher, see MySQL Enterprise Firewall Interface.

To install MySQL Enterprise Firewall manually, look in the share directory of your MySQL installation and choose the script that is appropriate for your platform. The available scripts differ in the suffix used to refer to the plugin library file:

- win_install_firewall.sql: Choose this script for Windows systems that use .dll as the file name suffix.
- linux_install_firewall.sql: Choose this script for Linux and similar systems that use .so as the file name suffix.

The installation script creates stored procedures in the default database, so choose a database to use. Then run the script as follows, naming the chosen database on the command line. The example here uses the mysql database and the Linux installation script. Make the appropriate substitutions for your system.

```
shell> mysql -u root -p mysql < linux_install_firewall.sql
Enter password: (enter root password here)
```

Installing MySQL Enterprise Firewall either using a graphical interface or manually should enable the firewall. To verify that, connect to the server and execute this statement:

Uninstalling MySQL Enterprise Firewall

MySQL Enterprise Firewall can be uninstalled using MySQL Workbench or manually.

To uninstall MySQL Enterprise Firewall using MySQL Workbench 6.3.4 or higher, see MySQL Enterprise Firewall Interface.

To uninstall MySQL Enterprise Firewall manually, execute the following statements. It is assumed that the stored procedures were created in the mysql database. Adjust the DROP PROCEDURE statements appropriately if the procedures were created in a different database.

```
DROP TABLE mysql.firewall_whitelist;

DROP TABLE mysql.firewall_users;

UNINSTALL PLUGIN mysql_firewall;

UNINSTALL PLUGIN mysql_firewall_whitelist;

UNINSTALL PLUGIN mysql_firewall_users;

DROP FUNCTION set_firewall_mode;

DROP FUNCTION normalize_statement;

DROP FUNCTION read_firewall_whitelist;

DROP FUNCTION read_firewall_users;

DROP FUNCTION mysql_firewall_lusers;

DROP FUNCTION mysql_firewall_flush_status;  # MySQL 5.6.26 and up only

DROP PROCEDURE mysql.sp_reload_firewall_rules;  # MySQL 5.6.26 and up only
```

6.4.3 Using MySQL Enterprise Firewall

Before using MySQL Enterprise Firewall, install it according to the instructions provided at Section 6.4.2, "Installing or Uninstalling MySQL Enterprise Firewall". Also, MySQL Enterprise Firewall does not work together with the guery cache; disable the guery cache if it is enabled (see Query Cache Configuration).

This section describes how to configure MySQL Enterprise Firewall using SQL statements. Alternatively, MySQL Workbench 6.3.4 or higher provides a graphical interface for firewall control. See MySQL Enterprise Firewall Interface.

To enable or disable the firewall, set the mysql_firewall_mode system variable. By default, this variable is enabled when the firewall is installed. To control the initial firewall state explicitly, you can set the variable at server startup. For example, to enable the firewall in an option file, use these lines:

```
[mysqld]
mysql_firewall_mode=ON
```

It is also possible to disable or enable the firewall at runtime:

```
mysql> SET GLOBAL mysql_firewall_mode = OFF;
mysql> SET GLOBAL mysql_firewall_mode = ON;
```

In addition to the global on/off firewall mode, each account registered with the firewall has its own operational mode. For an account in recording mode, the firewall learns an application's "fingerprint," that is, the acceptable statement patterns that, taken together, form a whitelist. After training, switch the firewall to protecting mode to harden MySQL against access by statements that deviate from the fingerprint. For additional training, switch the firewall back to recording mode as necessary to update the whitelist with new

statement patterns. As of MySQL 5.6.26, an intrusion-detection mode is available that writes suspicious statements to the error log but does not deny access.

The firewall maintains whitelist rules on a per-account basis, enabling implementation of protection strategies such as these:

- For an application that has unique protection requirements, configure it to use an account that is not used for any other purpose.
- For applications that are related and share protection requirements, configure them as a group to use the same account.

Firewall operation is based on conversion of SQL statements to normalized digest form. Firewall digests are like the statement digests used by the Performance Schema (see Performance Schema Statement Digests). However, unlike the Performance Schema, the relevant digest-related system variable is max_digest_length.

For a connection from a registered account, the firewall converts each incoming statement to normalized form and processes it according to the account mode:

- In recording mode, the firewall adds the normalized statement to the account whitelist rules.
- In protecting mode, the firewall compares the normalized statement to the account whitelist rules. If there is a match, the statement passes and the server continues to process it. Otherwise, the server rejects the statement and returns an error to the client. As of MySQL 5.6.25, the firewall also writes the rejected statement to the error log if the mysql_firewall_trace system variable is enabled.
- In detecting mode, the firewall matches statements as in protecting mode, but writes nonmatching statements to the error log without denying access.

Accounts that have a mode of OFF or are not registered with the firewall are ignored by it.

Note

Before MySQL 5.6.25, MySQL Enterprise Firewall records prepared statements as they are received by the server, not as normalized digests. Thus, spaces, tabs, and lettercase are signficant for comparison of whitelist rules against incoming statements.

To protect an account using MySQL Enterprise Firewall, follow these steps:

- 1. Register the account and put it in recording mode.
- 2. Connect to the MySQL server using the registered account and execute statements to be learned. This establishes the account's whitelist of accepted statements.
- 3. Switch the registered account to protecting mode.

The following example shows how to register an account with the firewall, use the firewall to learn acceptable statements for that account, and protect the account against execution of unacceptable statements. The example account, 'fwuser'@'localhost', is for use by an application that accesses tables in the sakila database. (This database is available at http://dev.mysql.com/doc/index-other.html.)

Note

The user and host parts of the account name are quoted separately for statements such as CREATE USER and GRANT, whereas to specify an account for use with a firewall component, name it as a single quoted string 'fwuser@localhost'.

The convention for naming accounts as a single quoted string for firewall components means that you cannot use accounts that have embedded @ characters in the user name.

Perform the steps in the following procedure using an administrative MySQL account, except those designated for execution by the account registered with the firewall. The default database should be sakila for statements executed using the registered account.

1. If necessary, create the account to be protected (choose an appropriate password) and grant it privileges for the sakila database:

```
mysql> CREATE USER 'fwuser'@'localhost' IDENTIFIED BY 'fWp@3sw0rd';
mysql> GRANT ALL ON sakila.* TO 'fwuser'@'localhost';
```

2. Use the sp_set_firewall_mode() stored procedure to register the account with the firewall and place it in recording mode (if the procedure is located in a database other than mysql, adjust the statement accordingly):

```
mysql> CALL mysql.sp_set_firewall_mode('fwuser@localhost', 'RECORDING');
```

During the course of its execution, the stored procedure invokes firewall user-defined functions, which may produce output of their own.

3. Using the registered account, connect to the server, then execute some statements that are legitimate for it:

```
mysql> SELECT first_name, last_name FROM customer WHERE customer_id = 1;
mysql> UPDATE rental SET return_date = NOW() WHERE rental_id = 1;
mysql> SELECT get_customer_balance(1, NOW());
```

The firewall converts the statements to digest form and records them in the account whitelist.

Note

Until the account executes statements in recording mode, its whitelist is empty, which is equivalent to "deny all." If switched to protecting mode, the account will be effectively prohibited from executing statements.

4. At this point, the user and whitelist information is cached and can be seen in the firewall INFORMATION_SCHEMA tables:

+-----

Note

The @@version_comment rule comes from a statement sent automatically by the mysql client when you connect to the server as the registered user.

It is important to train the firewall under conditions matching application use. For example, a given MySQL connector might send statements to the server at the beginning of a connection to determine server characteristics and capabilities. If an application normally is used through that connector, train the firewall that way, too. That enables those initial statements to become part of the whitelist for the account associated with the application.

5. Use the stored procedure to switch the registered user to protecting mode:

```
mysql> CALL mysql.sp_set_firewall_mode('fwuser@localhost', 'PROTECTING');
```

Important

Switching the account out of RECORDING mode synchronizes its firewall cache data to the underlying mysql system database tables for persistent storage. If you do not switch the mode for a user who is being recorded, the cached whitelist data is not written to the system tables and will be lost when the server is restarted.

6. Using the registered account, execute some acceptable and unacceptable statements. The firewall matches each one against the account whitelist and accepts or rejects it.

This statement is not identical to a training statement but produces the same normalized statement as one of them, so the firewall accepts it:

These statements do not match anything in the whitelist and each results in an error:

```
mysql> SELECT first_name, last_name FROM customer WHERE customer_id = 1 OR TRUE;
ERROR 1045 (28000): Statement was blocked by Firewall
mysql> SHOW TABLES LIKE 'customer%';
ERROR 1045 (28000): Statement was blocked by Firewall
mysql> TRUNCATE TABLE mysql.slow_log;
ERROR 1045 (28000): Statement was blocked by Firewall
```

As of MySQL 5.6.25, the firewall also writes the rejected statements to the error log if the mysql_firewall_trace system variable is enabled. For example:

```
[Note] Plugin MYSQL_FIREWALL reported:
'ACCESS DENIED for fwuser@localhost. Reason: No match in whitelist.
Statement: TRUNCATE TABLE `mysql` . `slow_log` '
```

You can use these log messages in your efforts to identify the source of attacks.

7. As of MySQL 5.6.26, you can log nonmatching statements as suspicious without denying access. To do this, put the account in intrusion-detecting mode:

```
mysql> CALL mysql.sp_set_firewall_mode('fwuser@localhost', 'DETECTING');
```

8. Using the registered account, connect to the server, then execute some statement does not match the whitelist:

```
mysql> SHOW TABLES LIKE 'customer%';
+------+
| Tables_in_sakila (customer%) |
+------+
| customer |
| customer_list |
```

In detecting mode, the firewall permits the nonmatching statement to execute but writes a message to the error log:

```
[Note] Plugin MYSQL_FIREWALL reported:
'SUSPICIOUS STATEMENT from 'fwuser@localhost'. Reason: No match in whitelist.
Statement: SHOW TABLES LIKE ? '
```

9. To assess firewall activity, examine its status variables:

The variables indicate the number of statements rejected, accepted, logged as suspicious, and added to the cache, respectively. The Firewall_access_granted count is 4 because of the @@version_comment statement sent by the mysql client each of the three time you used it to connect as the registered user, plus the SHOW TABLES statement that was not blocked in DETECTING mode.

Should additional training for an account be necessary, switch it to recording mode again, then back to protecting mode after executing statements to be added to the whitelist.

6.4.4 MySQL Enterprise Firewall Reference

The following discussion serves as a reference to these MySQL Enterprise Firewall components:

- Firewall tables in the mysql and INFORMATION SCHEMA databases
- · Firewall procedures and functions
- · Firewall system variables
- · Firewall status variables

6.4.4.1 MySQL Enterprise Firewall Tables

MySQL Enterprise Firewall maintains account and whitelist information. It uses INFORMATION_SCHEMA tables to provide views into cached data, and tables in the mysql system database to store this data in persistent form. When enabled, the firewall bases its operational decisions on the cached data.

The INFORMATION_SCHEMA tables are accessible by anyone. The mysql tables can be accessed only by users with privileges for that database.

The INFORMATION_SCHEMA.MYSQL_FIREWALL_USERS and mysql.firewall_users tables list registered firewall accounts and their operational modes. The tables have these columns:

• USERHOST

An account registered with the firewall. Each account has the format <code>user_name@host_name</code> and represents actual user and host names as authenticated by the server. Patterns and netmasks should not be used when registering users.

• MODE

The current firewall operational mode for the account. The permitted mode values are OFF, DETECTING (as of MySQL 5.6.26), PROTECTING, RECORDING, and RESET. For details about their meanings, see the description of sp_set_firewall_mode() in Section 6.4.4.2, "MySQL Enterprise Firewall Procedures and Functions".

The INFORMATION_SCHEMA.MYSQL_FIREWALL_WHITELIST and mysql.firewall_whitelist tables list registered firewall accounts and their whitelists. The tables have these columns:

• USERHOST

An account registered with the firewall. The format is the same as for the user account tables.

• RULE

A normalized statement indicating an acceptable statement pattern for the account. An account whitelist is the union of its rules.

6.4.4.2 MySQL Enterprise Firewall Procedures and Functions

MySQL Enterprise Firewall has stored procedures that perform tasks such as registering MySQL accounts with the firewall, establishing their operational mode, and managing transfer of firewall data between the cache and the underlying system tables. It also has a set of user-defined functions (UDFs) that provides an SQL-level API for lower-level tasks such as synchronizing the cache with the underlying system tables.

Under normal operation, the stored procedures implement the user interface. The UDFs are invoked by the stored procedures, not directly by users.

To invoke a stored procedure when the default database is not the database that contains the procedure, qualify the procedure name with the database name. For example:

```
CALL mysql.sp_set_firewall_mode(user, mode);
```

The following list describes each firewall stored procedure and UDF:

```
• sp_reload_firewall_rules(user)
```

This stored procedure uses firewall UDFs to reset a registered account and reload the in-memory rules for it from the rules stored in the <code>mysql.firewall_whitelist</code> table. This procedure provides control over firewall operation for individual accounts.

The user argument names the affected account, as a string in user_name@host_name format.

Example:

```
CALL mysql.sp_reload_firewall_rules('fwuser@localhost');
```

Warning

This procedure sets the account mode to RESET, which clears the account whitelist and sets its mode to OFF. If the account mode was not OFF prior to the sp_reload_firewall_rules() call, use sp_set_firewall_mode() to restore its previous mode after reloading the rules. For example, if the account was in PROTECTING mode, that is no longer true after calling sp_reload_firewall_rules() and you must set it to PROTECTING again explicitly.

• sp set firewall mode(user, mode)

This stored procedure registers a MySQL account with the firewall and establishes its operational mode. The procedure also invokes firewall UDFs as necessary to transfer firewall data between the cache and the underlying system tables. This procedure may be called even if the <code>mysql_firewall_mode</code> system variable is <code>OFF</code>, although setting the mode for an account has no operational effect while the firewall is disabled.

The user argument names the affected account, as a string in user_name@host_name format.

The *mode* is the operational mode for the user, as a string. These mode values are permitted:

- OFF: Disable the firewall for the account.
- DETECTING: Intrusion-detection mode: Write suspicious (nonmatching) statements to the error log but do not deny access.
- PROTECTING: Protect the account by matching incoming statements against the account whitelist.
- RECORDING: Training mode: Record acceptable statements for the account. Incoming statements that
 do not immediately fail with a syntax error are recorded to become part of the account whitelist rules.
- RESET: Clear the account whitelist and set the account mode to OFF.

Switching the mode for an account to any mode but RECORDING synchronizes the firewall cache data to the underlying mysql system database tables for persistent storage. Switching the mode from OFF to RECORDING reloads the whitelist from the mysql.firewall_whitelist table into the cache.

If an account has an empty whitelist, setting its mode to PROTECTING produces an error message that is returned in a result set, but not an SQL error:

```
| ERROR: PROTECTING mode requested for a@b but the whitelist is empty. | +-----+
1 row in set (0.02 sec)
Query OK, 0 rows affected (0.02 sec)
```

• mysql_firewall_flush_status()

This UDF resets several firewall status variables to 0:

```
Firewall_access_denied
Firewall_access_granted
Firewall_access_suspicious
```

Example:

```
SELECT mysql_firewall_flush_status();
```

• normalize_statement(stmt)

This UDF normalizes an SQL statement into the digest form used for whitelist rules.

Example:

```
SELECT normalize_statement('SELECT * FROM t1 WHERE c1 > 2');
```

• read_firewall_users(user, mode)

This aggregate UDF updates the firewall user cache through a SELECT statement on the mysql.firewall_users table.

Example:

```
SELECT read_firewall_users('fwuser@localhost', 'RECORDING')
FROM mysql.firewall_users;
```

• read_firewall_whitelist(user, rule)

This aggregate UDF updates the recorded statement cache through a SELECT statement on the mysql.firewall_whitelist table.

Example:

```
SELECT read_firewall_whitelist('fwuser@localhost', 'RECORDING')
FROM mysql.firewall_whitelist;
```

• set firewall mode(user, mode)

This UDF manages the user cache and establishes the user operational mode.

Example:

```
SELECT set_firewall_mode('fwuser@localhost', 'RECORDING');
```

6.4.4.3 MySQL Enterprise Firewall System Variables

MySQL Enterprise Firewall supports the following system variables. Use them to configure firewall operation. These variables are unavailable unless the firewall is installed (see Section 6.4.2, "Installing or Uninstalling MySQL Enterprise Firewall").

mysql firewall max query size

Introduced	5.6.24	
Removed	5.6.26	
Command-Line Format	mysql	firewall_max_query_size=size
System Variable	Name	mysql_firewall_max_query_size
	Variable Scope	Global
	Dynamic Variable	
Permitted Values	Туре	integer
	Default	4096
	Min Value	0
	Max Value	4294967295

The maximum size of a normalized statement that can be inserted in the MySQL Enterprise Firewall cache. Normalized statements longer than this size are truncated. Truncated statements are discarded if the firewall mode for the current user is RECORDING and rejected if the mode is PROTECTING.

mysql_firewall_max_query_size was removed in MySQL 5.6.26. max_digest_length should be set large enough to avoid statement truncation.

• mysql_firewall_mode

Introduced	5.6.24	
Command-Line Format	mysql	firewall_mode={OFF ON}
System Variable	Name	mysql_firewall_mode
	Variable Scope	Global
	Dynamic Variable	
Permitted Values	Туре	boolean
	Default	ON

Whether MySQL Enterprise Firewall is enabled (the default) or disabled.

mysql_firewall_trace

Introduced	5.6.24
Command-Line Format	mysql_firewall_trace={OFF ON}

System Variable	Name	mysql_firewall_trace
	Variable Scope	Global
	Dynamic Variable	
Permitted Values	Туре	boolean
	Default	OFF

Whether the MySQL Enterprise Firewall trace is enabled or disabled (the default). When enabled, mysql firewall trace has this effect:

- In MySQL 5.6.24, the firewall writes a file named firewall_trace.txt in the data directory.
- In MySQL 5.6.25 and higher, for PROTECTING mode, the firewall writes rejected statements to the error log.

6.4.4.4 MySQL Enterprise Firewall Status Variables

MySQL Enterprise Firewall supports the following status variables. Use them to obtain information about firewall operational status. These variables are unavailable unless the firewall is installed (see Section 6.4.2, "Installing or Uninstalling MySQL Enterprise Firewall"). Firewall status variables are set to 0 whenever the MYSQL_FIREWALL plugin is installed or the server is started. Many of them are reset to zero by the mysql_firewall_flush_status() UDF (see Section 6.4.4.2, "MySQL Enterprise Firewall Procedures and Functions").

• Firewall_access_denied

The number of statements rejected by MySQL Enterprise Firewall.

• Firewall_access_granted

The number of statements accepted by MySQL Enterprise Firewall.

• Firewall_access_suspicious

The number of statements logged by MySQL Enterprise Firewall as suspicious for users who are in DETECTING mode.

• Firewall_cached_entries

The number of statements recorded by MySQL Enterprise Firewall, including duplicates.

Appendix A MySQL 5.6 FAQ: Security

Questions

- A.1: Where can I find documentation that addresses security issues for MySQL?
- A.2: Does MySQL 5.6 have native support for SSL?
- A.3: Is SSL support built into MySQL binaries, or must I recompile the binary myself to enable it?
- A.4: Does MySQL 5.6 have built-in authentication against LDAP directories?
- A.5: Does MySQL 5.6 include support for Roles Based Access Control (RBAC)?

Questions and Answers

A.1: Where can I find documentation that addresses security issues for MySQL?

The best place to start is Chapter 1, Security.

Other portions of the MySQL Documentation which you may find useful with regard to specific security concerns include the following:

- · Section 2.1, "Security Guidelines".
- Section 2.3, "Making MySQL Secure Against Attackers".
- · How to Reset the Root Password.
- · Section 2.5, "How to Run MySQL as a Normal User".
- UDF Security Precautions.
- Section 2.4, "Security-Related mysqld Options and Variables".
- Section 2.6, "Security Issues with LOAD DATA LOCAL".
- Chapter 3, Postinstallation Setup and Testing.
- Section 5.9, "Using Secure Connections".

A.2: Does MySQL 5.6 have native support for SSL?

Most 5.6 binaries have support for SSL connections between the client and server. See Section 5.9, "Using Secure Connections".

You can also tunnel a connection using SSH, if (for example) the client application does not support SSL connections. For an example, see Section 5.11, "Connecting to MySQL Remotely from Windows with SSH".

A.3: Is SSL support built into MySQL binaries, or must I recompile the binary myself to enable it?

Most 5.6 binaries have SSL enabled for client/server connections that are secured, authenticated, or both. See Section 5.9, "Using Secure Connections".

A.4: Does MySQL 5.6 have built-in authentication against LDAP directories?

The Enterprise edition includes a PAM Authentication Plugin that supports authentication against an LDAP directory.